




Wirecast 6.0 User Guide for Mac

Contents

Preface 11

Copyright and Trademark Notice	11
MPEG-2 License Requirements	11
Customer Support	12
We'd Like to Hear from You!	12
Limited Warranty and Disclaimers	12
Warranty Remedies	12
Software Updates	13
Restrictions and Conditions of Limited Warranty	13
Limitations of Warranties	13

Introduction 15

Introduction	15
Topics	15
Editions and Options	15
Editions	15
Options	16
Wirecast Workflow	16
Tutorials	18
Two Ways to Use this Application	18
Presenter Is Operator	19
Presenter Plus Operator	19
Using AutoLive	20
Main Window Layout	20
Preview	22
Master Audio	23
Main Shot List	24
Control/Status Bar	24
Layers	26
Layer Windows	27
Scripting APIs	27

Installation 29

- Introduction 29
 - Topics 29
- Installing 29
- Activating 30
- Uninstalling 31
- System Requirements 31

Tutorials 33

- Introduction 33
 - Tutorials 33
- Tutorial 1: Basic Concepts 34
 - Tutorial Prep 34
 - The Main Window 36
 - What Is a Shot? 36
 - Switching Between Shots 37
 - Transitions 38
 - Transition Speed 39
 - Go Button 39
 - Layers 40
 - Auto Live 41
 - Turn AutoLive Off 42
 - Multiple Changes 43
 - Preview 43
- Tutorial 2: Editing Shots 46
 - Shot Editor Overview 47
 - Source Layers 49
 - Template Window 49
 - Titles 52
 - Effects/Motion 54
 - Positioning Objects 54
 - Motion for Objects 56
 - Changing Motion Options 56
- Tutorial 3: Broadcasting 57
 - Streaming 57

Main Window 61

- Introduction 61
 - Topics 61
- Overview 61
- Control/Status Bar 62
- Preview / Live Broadcast Area 63
- Countdown Clock Display 65
- Transition Controls 65
 - Changing Transitions 65
 - Transition Speed 66

Go Button	66
Transition Editing	66
Shot Tool Menu	67
Live Sources	67
Shot Audio	68
Desktop Presenter	68
File Sources	68
Shot Selection Area	68
Changing Shots	69
Moving a Shot to Another Layer	71
Resizing the Shot Icons	71
Layers	71
What is a Layer?	72
Changing Layers	73
Moving a Shot to Another Layer	73
Layer Zooming	73
AutoLive	74
Live Icons	74

Keyboard Shortcuts 77

Introduction	77
General Shortcuts	77
WirecastUstream Menu	77
File Menu	78
Edit Menu	78
Switch Menu	78
Media Menu	78
Source Menu	78
Output Menu	78
Layout Menu	78
Replay Menu	78
Social Menu	78
Window Menu	78
Help Menu	78

Adding Media 79

Introduction	79
Topics	79
Images/Opacity	79
GIF and Transparency	79
Keynote Movies	80
Exporting from Keynote	80
Using Movies	80
Windows Media	81
Real Media	81
Supported Codecs	81

Titles 83

- Introduction 83
 - Topics 83
- Adding Titles 83
 - Adding New Source 84
 - Configuring Titles 85
- Modifying Titles 86
- Title Area 86
 - Changing Text 86
 - Changing Justification 87
 - Changing Font 87
 - Changing Font Color 87
- Placing Titles 87
 - Seminar Title 87
 - Interview Title 88
- Creating New Templates 88
 - Example 88
 - Other Media 88
 - Editing XML Files 88

Logos 89

- Introduction 89
 - Topics 89
- Global Logos 89
 - Turning Layers On and Off 96
- Shot Logos 96

Shot Editor 101

- Introduction 101
 - Topics 101
- Overview 102
 - The Inspector 102
 - Activating Changes 102
 - Inspector vs. Editor 102
- Shot Editor Layout 103
- Sources 104
 - Templates 104
 - Virtual Sets 106
 - Controlling Source Visibility 107
- Shot Editor Preview 107
- Shot Editor Media Panel 109
 - Live Feed Sources 109
 - Media File Sources 110
 - Title Banner Sources 110
- Shot Editor Effects 111
 - Opacity 112

Matte	112
Aspect Ratio	113
Reposition Buttons	113
Shot Editor Cropping	114
Shot Editor Chroma Key	114
Working Top Down	114
Selecting a Key Color	115
Key Threshold	115
Black Clip	115
White Clip	115
Getting a Good Key	115
Lighting	115
Good Camera	116
High Quality Video	116
Shot Editor Motion	117
Shot Editor Playback	118
Live Playback	119
Scrubbing	119
Transport Controls	119
In and Out Points	120
When Finished Control	120
Begin Playing Control	120
Remember Position Control	121
Audio Controls	121
Shot Editor Filter	121
Modifying the Filter Parameters	122

Source Settings 123

Introduction	123
Topics	123
Overview	123
System Devices	124
Scoreboards	125
The Data Tab	127
The Look Tab	127
Teradek Cube	129
Remote Desktop Presenter	129
Local Desktop Presenter	130
Wirecast Cam	133
Wirecast Cam App	133
Wirecast Cam Dashboard	134
Wirecast Cam Settings	135
Starting Your Wirecast Cam Broadcast	135
Adding a Wirecast Cam Source	136
Web Stream	139
Capture Cards	140
Blackmagic	141

Show USB Devices 143

Playlist 145

Introduction 145

Topics 145

Creating a Playlist 146

Adding Clips 147

Playing Playlists 150

Playlist Controls 150

Restoring Playlist Position 152

Countdown Clock Options 152

Social Media 155

Introduction 155

Topics 155

Settings 155

Message Feed 156

Create Shot 157

Replay 159

Introduction 159

Topics 159

Replay Settings 160

Replay Activation 161

Replay Templates 164

Audio Inspector 169

Introduction 169

Topics 169

Overview 169

Hardware Audio and Shot Audio 170

Hardware Audio 171

Shot Audio 171

Adding Shot Audio Sources 171

Managing Audio Sources 172

Preferences 173

Introduction 173

Topics 173

Accessing Preferences 173

Resetting Preferences 174

General 174

Open Last Document on Startup 174

Shot Editor Checkerboard 174

Feedback Detection	175
Maximum Reconnection Attempts	175
Performance	175
Licenses	176
Serial Numbers	176
Manual Activation	177
Deactivate Serial Numbers	177
Demonstration Mode	177
Software Update	178
Automatically Check Updates	178
Check Now	178
Advanced	178
Use High Quality Video	179
YUV Colorspace	179
Disable ONVIF IP Camera Discovery	179
Disable Bonjour IP Camera Discovery	179

Asset Manager 181

Introduction	181
Topics	181
Documents	181
Re-assigning Media	181

Menus and Windows 183

Introduction	183
Topics	183
Wirecast Menu	183
File Menu	184
Edit Menu	184
Switch Menu	185
Media Menu	185
Sources Menu	186
Output Menu	186
Layout Menu	187
Replay Menu	187
Social Menu	188
Window Menu	188
Help Menu	189

Broadcasting 191

Introduction	191
Topics	191
Canvas Size	192
Virtual Camera	193
Configuring Output Settings	194
Multiple Output Settings	195

Configuration	195
Encoder Presets	196
Multicast and Unicast	199
Flash RTMP Server	200
CDN Partners	201
Flash To Bambuser, Churchstreaming.tv, DaCast Streaming Services, High School Cube, iNK Barrel Video, Livebeats, make.tv, Meridix Sports Network, Netbriefings, ShowCaster, Streaming Media Hosting, StreamVu, Stretch Internet, Sunday Streams, Tulix, Ustream	201
Flash To Microsoft Azure, Brightcove, Limelight, Sermon.net	203
Flash To Akamai	204
Flash To TwitchTV	205
Flash To YouTube	206
Flash To Zixi	207
Streaming	208
Record To Disk	209

Encoder Presets 211

Introduction	211
Topics	211
The Encoder Presets Window	211
Creating New Presets	212
Profile Options	212
MainConcept H.264	213
x264	216

Making Great Presentations 219

Introduction	219
Topics	219
Overview	219
High Quality Audio	220
Good Lighting	220
Triangular Lighting	221
Broadcast Settings	222
Bandwidth	222
Motion	222
Encoder Settings	222

Acknowledgments 223

Acknowledgments	223
Overview	223
Darwin streaming server	223
FFmpeg Project	229

Preface

Copyright and Trademark Notice

Copyright 2014 Telestream, Inc. All rights reserved. No part of this publication may be reproduced, transmitted, transcribed, altered, or translated into any languages without written permission of Telestream, Inc. Information and specifications in this document are subject to change without notice and do not represent a commitment on the part of Telestream.

Telestream, CaptionMaker, Episode, Flip4Mac, FlipFactory, Flip Player, Lightspeed, ScreenFlow, Vantage, Wirecast, GraphicsFactory, MetaFlip, MotionResolve, and Split-and-Stitch are registered trademarks and Pipeline, MacCaption, e-Captioning, and Switch are trademarks of Telestream, Inc. All other trademarks are the property of their respective owners..

QuickTime, Mac OS X, Final Cut Pro, and Safari are trademarks of Apple, Inc. Bonjour, the Bonjour logo, and the Bonjour symbol are trademarks of Apple, Inc.



All other brand, product, and company names are property of their respective owners, and are used only for identification purposes.

MPEG-2 License Requirements

Telestream has obtained a license from MPEG LA, to produce MPEG-2 video, to meet the following requirement on behalf of its FlipFactory and Pipeline licensees: The use of this product in any manner that complies with the MPEG-2 standard is expressly prohibited without a license under applicable patents in the MPEG-2 patent portfolio, which license is available from MPEG LA, L.L.C., 250 Steele Street, Suite 300, Denver, Colorado 80206.

Customer Support

Telestream offers technical support through our Web site and email.

Email contacts:

- Sales: sales@telestream.net
- Support: desktopsupport@telestream.net

Website Links:

- How to Buy: <http://www.telestream.net/purchase/store.htm>
- Support: <http://www.telestream.net/telestream-support/wire-cast/support.htm>

We'd Like to Hear from You!

Telestream welcomes comments, feedback, and suggestions about your experience with Wirecast. You can reach us at support@telestream.net.

If you have suggestions about improving the tutorials or this guide, other Telestream documents, or our Web site, please email us at techwriter@telestream.net.

Limited Warranty and Disclaimers

Telestream, Inc. (the Company) warrants to the original registered end user that the product will perform as stated below for a period of one (1) year from the date of shipment from factory:

Hardware and Media. The Product hardware components, including equipment supplied but not manufactured by the Company but NOT including any third party equipment that has been substituted by the Distributor for such equipment (the "Hardware"), will be free from defects in materials and workmanship under normal operating conditions and use.

Software. If software is supplied as part of the product, the software will operate in substantial conformance with specifications set forth in its product user's guide. The Company does not warrant that the software will operate uninterrupted or error-free, will meet your requirements, or that software errors will be corrected.

Warranty Remedies

Your sole remedies under this limited warranty are as follows:

Hardware and Media. The Company will either repair or replace (at its option) any defective Hardware component or part, or Software Media, with new or like new Hardware components or Software Media. Components may not be necessarily the same, but will be of equivalent operation and quality.

Software. If software is supplied as part of the product and it fails to substantially conform to its specifications as stated in the product user's guide, the Company shall, at its own expense, use its best efforts to correct (with due allowance made for the nature and complexity of the problem) such defect, error or nonconformity.

Software Updates

If software is supplied as part of the product, the Company will supply the registered purchaser/licensee with maintenance releases of the Company's proprietary Software Version Release in manufacture at the time of license for a period of one year from the date of license or until such time as the Company issues a new Version Release of the Software, whichever first occurs. To clarify the difference between a Software Version Release and a maintenance release, a maintenance release generally corrects minor operational deficiencies (previously non-implemented features and software errors) contained in the Software, whereas a Software Version Release adds new features and functionality. The Company shall have no obligation to supply you with any new Software Version Release of Telestream software or third party software during the warranty period, other than maintenance releases.

Restrictions and Conditions of Limited Warranty

This Limited Warranty will be void and of no force and effect if (i) Product Hardware or Software Media, or any part thereof, is damaged due to abuse, misuse, alteration, neglect, or shipping, or as a result of service or modification by a party other than the Company, or (ii) Software is modified without the written consent of the Company.

Limitations of Warranties

THE EXPRESS WARRANTIES SET FORTH IN THIS AGREEMENT ARE IN LIEU OF ALL OTHER WARRANTIES, EXPRESS OR IMPLIED, INCLUDING, WITHOUT LIMITATION, ANY WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. No oral or written information or advice given by the Company, its distributors, dealers or agents, shall increase the scope of this Limited Warranty or create any new warranties.

Geographical Limitation of Warranty. This limited warranty is valid only within the country in which the Product is purchased/licensed.

Limitations on Remedies. YOUR EXCLUSIVE REMEDIES, AND THE ENTIRE LIABILITY OF TELESTREAM, INC. WITH RESPECT TO THE PRODUCT, SHALL BE AS STATED IN THIS LIMITED WARRANTY. Your sole and exclusive remedy for any and all breaches of any Limited Warranty by the Company shall be the recovery of reasonable damages which, in the aggregate, shall not exceed the total amount of the combined license fee and purchase price paid by you for the Product.

Damages. TELESTREAM, INC. SHALL NOT BE LIABLE TO YOU FOR ANY DAMAGES, INCLUDING ANY LOST PROFITS, LOST SAVINGS, OR OTHER INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF YOUR USE OR INABILITY TO USE THE PRODUCT, OR THE BREACH OF ANY EXPRESS OR IMPLIED WARRANTY, EVEN IF THE COMPANY HAS BEEN ADVISED OF THE POSSIBILITY OF THOSE DAMAGES, OR ANY REMEDY PROVIDED FAILS OF ITS ESSENTIAL PURPOSE.

Further information regarding this limited warranty may be obtained by writing:

Telestream, Inc.
848 Gold Flat Road
Nevada City, CA 95959

You can call Telestream, Inc. via telephone at (530) 470-1300.

Introduction

Introduction

This guide is intended to help you understand how each feature of Wirecast operates and to provide you with information to help you make the best presentations possible.

Topics

- *Editions and Options*
- *Wirecast Workflow*
- *Tutorials*
- *Two Ways to Use this Application*
- *Using AutoLive*
- *Main Window Layout*
- *Scripting APIs*

Editions and Options

Wirecast is available in multiple editions. The editions of Wirecast, each with its own set of features, are presented in this guide. The term Wirecast is used, generally, to describe all major features.

Editions

Wirecast is available in two editions: *Studio* and *Pro*.

Wirecast *Studio* allows an unlimited number of cameras and inputs, titling overlays, chroma keys, multiple layers, shot editing, and the ability to preview shots prior to broadcast.

Features that pertain specifically to Wirecast Studio are indicated by the *Studio* icon (shown below):

STUDIO

Wirecast *Pro* is the professional edition of Wirecast and includes all the features of Wirecast *Studio*. It adds an audio inspector, advanced audio controls, virtual sets, scoreboards, and many other professional features. Features that pertain specifically to Wirecast *Pro* are indicated by the *Pro* icon (shown below):

PRO

Options

STUDIO

Wirecast *Studio* provides support for multiple cameras and inputs, selected Blackmagic, Osprey by Variosystems, and Matrox Multi capture cards and LiveU video-over-cellular backpack. Users can broadcast their computer desktop (including computer audio) using Desktop Presenter. Other key features include chroma key support, 3D graphics, titles, transitions and up to 35 layers of live compositing. Additionally, you can use HDV when you purchase an HDV option license. Without the license you can still experiment with HDV input, but all HDV output is water-marked.

PRO


Wirecast *Pro* provides Virtual Sets (a library of professionally designed 3D sets), a powerful Audio Inspector with synch delay, Web stream support, integration with Teradek Cube. Wirecast *Pro* also provides live scoreboards and includes the HDV option license which adds support for HDV codec encoding.

Note: If you do not have a Wirecast *Pro* or *Studio* license, Wirecast still enables you to experiment with *Pro* or *Studio* features, but all Wirecast *Pro* and *Studio* output is water-marked. Additionally, you can not save a document that has *Pro* or *Studio* features enabled.

Wirecast Workflow

Wirecast is a powerful cross-platform live video switching, production, and encoding software. Because of its versatility in handling a variety of inputs and outputs, it typically fits in the middle of your broadcasting workflow. Wirecast can take the place of more traditional *T-bar* hardware switchers, graphics and title generators, or simply act as the backend encoder for large switching systems.

Below is a diagram of the basic Wirecast workflow. In general, you will capture your live input devices (such as live camera feeds, iOS cameras, computer desktop, web feeds and more), produce your show using the full range of Wirecast's production features (chroma key, graphics, titles, scoreboards, etc.), and then stream it live to web, LAN, or record locally.



Wirecast works with cameras, capture cards, audio devices. It prepares media and then outputs it either by streaming to the Internet, CDNs, multicast/unicasts via LAN, locally via virtual output or second display, or Pro's Blackmagic Output feature.



Tutorials

We suggest that you first work through the tutorials in the [Tutorials](#) section. They are quick, informative, and the easiest way to become familiar with Wirecast.

Wirecast provides a built-in tutorial environment that corresponds with the tutorials provided in [Tutorials](#). The tutorials take about thirty minutes and provide a brief overview of how to set up a basic presentation and create your own broadcast.

Next, we suggest that you read [Making Great Presentations](#). This topic shows you how you can easily make changes in your setup and improves the quality of your presentations.

Two Ways to Use this Application

There are two different ways you can use Wirecast:

- **Presenter Is Operator** The person conducting the presentation also operates Wirecast.
- **Presenter Plus Operator** The presenter concentrates on the content and someone else operates Wirecast. In this mode, the presenter never needs to know in detail how Wirecast works.

Presenter Is Operator

In this mode of operation, the person conducting the presentation simultaneously operates Wirecast.

Here are some suggestions for using Wirecast when you are both the presenter and operator:

- **Keep it simple** Set up Wirecast to make it easy for you to be the operator and the presenter. Set up your logo and titles so that you need to make very few changes during your presentation. Use a minimum number of shots so it's easy for you to see which shot to choose.
- **Keep the AutoLive feature on** This enables you to present your shots with just one click. Though this limits your ability to perform complex presentations, it is the best way when the presenter is also the operator. To turn AutoLive on or off, select it under the Switch menu.
- **Pre-configure your shots** Make sure that all the shots are created prior to your presentation. Do not try to create or modify shots while broadcasting them.
- **Use hot-keys for switching shots** If your shot has a number in its name, you can press the Option key plus that number's key to immediately display the shot. For example, if you have a shot named "Me With Title 1", press the Option key and the 1 key to display this shot. Make sure you rename a shot and add a number to take advantage of using hot keys.

Presenter Plus Operator

STUDIO

In this mode of operation, an engineer (or operator) is responsible for using Wirecast, and the presenter concentrates on the content of the presentation.

Here are some suggestions for using Wirecast when you have both an operator and a presenter:

- **Keep the AutoLive feature off** This enables you to make several changes at one time before taking the changes live. However, to quickly make a shot live, press the Command+Ctrl keys and click the shot.
- **Open the Preview window** The operator should use Preview mode to examine everything before it becomes live.
- **Use the Layer Windows to make more shots available** Select New Layer Window from the Window menu to open additional layer windows so you can quickly flip between shots on several layers.
- **Use the Inspector window to open and edit shots** The Inspector window acts exactly like the edit window but always edits the last shot you changed. To open the Inspector Window, click on the Window menu and select Inspector.

Using AutoLive

Some users of Wirecast may want to single-click a shot to make it become live. Other users may want to make several changes to the broadcast before making them live. You can use both methods in Wirecast.

The AutoLive feature is designed to offer a single-click operation for those users who want to simply click from shot to shot. The Edit window (or other windows) is not affected by the status of AutoLive.

When AutoLive is on, clicking a shot in the Main Window makes it become live. As a result, the Go button becomes inactive. Command+Ctrl+Click loads a shot into the preview but does not make it live.




When AutoLive is off, you click on a shot in the Main Window to display it in Preview, then the Go button is required to make the shot live. Command+Ctrl+Click takes a shot live immediately.


Sometimes you may want to temporarily turn on and off (toggle) the AutoLive state. Hold down the Command and control keys at the same time to temporarily turn on Autolive. This enables you to quickly switch AutoLive on for one action (i.e. a mouse-click), then off again.

Main Window Layout

Wirecast enables you to select which functions are displayed in the Main window. These functions are added or removed from the main window using the Layout menu.




There are three layout options: Preview, Master Audio, and Main Shot List. Each option represents a pane in the Main window and is turned on or off by selecting it. A check mark indicates that the option is turned on.



Preview


STUDIO

Preview displays what the broadcast will look like when you click the Go button. (The Go button is only active when AutoLive is off.) To display the Preview window, click select *Layout > Preview*.



Master Audio

The Master Audio panel enables you to control the output volume level, mute audio output, and mute the line-out feed for Preview and Live displays. To display Master Audio for Preview and Live displays, click *Layout > Master Audio*. Click again to hide the Master audio controls.




The Preview and Live Master Volume controls enable you to adjust the master audio volume for Preview and Live separately. Click and drag the slider control up or down to set the volume. The decibel scale next to the slider indicates the audio level. When you take a Preview shot live, the Live audio controls are set to the levels set in Preview.

The Master Mute button controls the mute of the Live master audio (what your viewers hear). Even when you mute the output, the encoder still generates audio but it is silent. If you don't want to broadcast audio, modify the Encoder Presets to not process audio through the encoder.

The Preview and Live Line-Out Mute buttons control what you hear locally. When line-out is muted, audio is not sent to your headphones or speakers, but your viewers still hear it. The two controls are mutually exclusive -- you cannot have both on at the same time, but you can mute both.


Main Shot List

Normally, the Main Window displays the shot list at the bottom of the window. However, you can hide the shot list display by unchecking *Main Shot List* in the Layout Menu. This is useful if you want to open up multiple Shot List Layer windows.



Control/Status Bar

Control buttons and status information are displayed at the top of the Main window.



Wirecast displays the following controls and statistics:

- **Stream button** Click to begin streaming.
- **Streaming time** This displays how long you have been streaming. This value does not reset when you start/stop the broadcast. It is cumulative. This enables you to save portions of a broadcast to disk and still know the total amount of time.
- **Record Button** Click to begin recording.
- **Recording Time** This displays how long you have been recording. This value does not reset when you start/stop the broadcast. It is cumulative.
- **Gear Icon** This is an Output Settings shortcut. Click to open the Output Settings window. (Same as selecting *Output > Output Settings*).

- **Frames per Second** Displays the broadcast frame rate (FPS).
- **Bitrate** Displays the broadcast bitrate (kilobits per second).
- **CPU usage (percentage)** This displays the current load on your CPU when streaming or recording in percent of usage. The encoder affects the CPU usage more than any other parameter in Wirecast. If this value is high, you should use a different encoder, or modify your encoder settings. If the CPU usage is near 95%, use a lower quality video output to lower the bandwidth.


Note: To avoid decrease in video quality, Wirecast should not be used at CPU usage above 80%. See the Telestream Web site for suggested configurations.

- **Connection** This displays the current connection quality. The bars indicate the amount of buffer memory used. High bar count reflects low buffer use (good connection). Low bar count reflects high buffer use (poor connection and in danger of broadcast errors). When one orange bar is displayed, the buffer is full.

Layers

STUDIO


Wirecast displays five layers in the Main Shot List window. They are numbered 1 through 5 along the right side of the window. Each layer contains shots that can be selected by clicking them. A red LED light indicates that a shot is Live. (If AutoLive is turned on, when a shot is selected it is displayed in the Live window.) If you select multiple shots -- by selecting shots on multiple layers -- they will all be displayed in the Live window. But the shots are displayed in a layering manner, where layer 1 is on top and layer 5 is at the bottom (and layers 2 through 4 are layered in between). In the example below, the Logo in layer 2 is displayed on top of the River shot in layer 3.



Layer Windows

STUDIO +

You can also open the Shot List in a separate window. Select *Window > New Layer Window* to display a list of the layer windows you can open (Master Layer 1 through 5). Select the layer you want to open and a new, separate layer window is displayed.



This panel works exactly like the Shot List panel in the Main window, but enables you to open multiple layer panels. You can change which layer is displayed on each panel by selecting the *Windows* menu and selecting a different layer.

Scripting APIs

Wirecast provides scripting which enables you to control and automate the Wirecast environment.

Scripting is all handled via AppleScript. To access the documentation, open up Apple Script Editor (select *Applications -> Utilities -> Apple Script Editor*), then select *File -> Open Dictionary*, and select the */Applications/Wirecast.app* bundle from the list.

Installation

Introduction

This topic guides you through installing (or upgrading) and activating Wirecast.

Topics

- *Installing*
- *Activating*
- *Uninstalling*

Installing


To install Wirecast, follow these steps:

1. Download the installer from the Website at:
<http://www.telestream.net/wirecast/overview.htm>.

Note: During installation, you will be asked if you want to install the Virtual Microphone feature. If you do (recommended), check the displayed check box and continue the installation. Installing Virtual Microphone requires administrative rights.

2. Run the installer (.dmg) program.
3. Click Agree to the license terms.

4. Open the Wirecast in the downloads folder, then click and drag the icon into the Applications folder. If a version of Wirecast already exists, the installer asks you if you want to replace the previous version.




Activating


When you purchased Wirecast a serial number was provided. This serial number must be registered in the Wirecast program to unlock the features of Wirecast. To register Wirecast follow these steps:

1. Run the Wirecast program.

2. Select *Preferences* from the Wirecast menu, select *Licenses*, then click *Purchase License*.



3. Enter your serial number. (If you do not have a license, click *Purchase* to purchase a license on-line.)



4. When the unlocked message displays, click OK.
5. Close the Preferences window.

Your Wirecast program should now be fully activated.

Uninstalling

1. To uninstall Wirecast, place the Wirecast program in the Trash folder.

System Requirements

Wirecast

- Operating Systems: OS X 10.9 Mavericks and OS X 10.10 Yosemite (Wirecast 6 does not support OS X 10.8 or previous versions)
- Mac computer with Intel Core 2 Duo processor
- Core i5 or later recommended for 720p streaming
- Core i7 recommended for 1080p streaming
- 2GB RAM minimum

- 4GB recommended for 1080p streaming
- 200MB free hard drive space for installation
- Hard drive space for recording to disk
- Compatible Flash streaming server, or account with a supported Flash streaming portal required for Flash H.264 streaming
- 512 MB PCI-Express graphics card with 3D acceleration
- GeForce or Radeon class card recommended
- Sufficient upload speed for streaming
- Minimum recommended is twice the bandwidth of the total bit rate of the stream

Desktop Presenter

- Use the remote version of Desktop Presenter 2.0.5 with Wirecast 6.0; it's available as a separate download at: <http://www.telestream.net/purchase/store.htm>.

Tutorials

Introduction

The best way to get started using Wirecast is to quickly work through all its main features. This tour presents a series of three tutorials, each designed to help you understand how to create and broadcast presentations using Wirecast.

As you work through these tutorials, you will also become familiar with important Wirecast concepts and how you can use them to deliver high quality broadcasts. The more you know about Wirecast, the better it will serve your broadcasting objectives.

Because each tutorial builds on the skills and knowledge you learn in the previous tutorials, it is recommended that you take the tutorials in succession. Working through all the tutorials takes about thirty minutes.

As you gain hands-on experience creating video and audio presentations - which leads to a working knowledge of Wirecast and its components and architecture - you will gain proficiency in using Wirecast.

Tutorials

- *Tutorial 1: Basic Concepts*
- *Tutorial 2: Editing Shots*
- *Tutorial 3: Broadcasting*


Note: You can run all of the tutorials without a license. However, a watermark on the video and an occasional voice-over on the audio are present until a valid license is activated.

Note: For licensing information, select Preferences from the Wirecast menu, select *License*, then click *Purchase License*. Or, you can contact sales@telestream.net.

Tutorial 1: Basic Concepts

The goal of this tutorial is to provide you with a quick but successful experience creating and broadcasting a presentation using Wirecast.

This tutorial requires that you open the tutorial document in Wirecast. To do this, select *Create Document for Tutorial* from the Help menu in Wirecast.




Note: If you are running the tutorial with Wirecast in demonstration mode, the Wirecast logo appears from time to time and audio output has a periodic voice-over.

Tutorial Prep

To prepare for this tutorial you need to make two changes.

First, select *Switch > Auto Live* to turn on the Auto Live option. But also select *Layout > Preview* to turn off the Preview option. Both of these options will be changed back later in the tutorial.


The Wirecast Main Window shows the AutoLive LED as turned on.



AutoLive LED on

The Main Window

Wirecast has two main display areas: Live Broadcast and Shot List. The Live Broadcast area is in the upper portion of the window displaying what Wirecast broadcasts to your viewers (or what it records to disk). The Shot List, in the lower half of the window, displays the shots available for broadcast.




What Is a Shot?

Wirecast uses the concept of a shot to construct presentations. A shot contains media, along with the settings for that media. In its simplest form, a shot contains one piece of media such as a photo or a video clip. But it can also be something more complex, like a live camera with a title, and background music, or even a Playlist of shots.

A shot can be edited and its settings can be changed (See [Tutorial 2: Editing Shots](#)). Shots are important because they enable you to configure a lot of information before you broadcast your presentation. This enables you to concentrate on creating a good production during your broadcast.


Switching Between Shots

Individual shots are displayed in the Shot List. Click the Ripples shot in the Shot List area and the image fades into the Live Broadcast Area display. This is called “taking a shot live”.



Click the shot labeled Blank Shot and the Ripples image fades to a blank screen. The Blank Shot enables you to display nothing, which is sometimes useful.

Blank Shot in Live Broadcast Area




Click Blank Shot

Transitions

In the previous examples, a fade occurred when you clicked on a shot. This is because a smooth transition is the default.


Transition controls are located just below the Live Broadcast Area where two kinds of transitions are shown: Cut and Smooth.




When Cut is selected, transitions are immediate. When Smooth is selected, transitions fade in (as demonstrated above).

There are more than just two kinds of transitions to choose from, but only two can be assigned to the Transition Panel. To select a different transition type, click the small arrow on the right side of either transition button. When the list appears, select a new

transition to assign to the button. You can also click the transition button and drag the mouse downward until the menu of selections is displayed.



For example, to change the first transition button from Cut to Swoop, click the Cut button and dragging downward until the menu appears. select *Swoop* from the menu. Swoop should now be selected for the first button.




Now click back and forth between River and Ripples using Swoop.

These two transition buttons can also be selected by using the following key combinations: Command+1 and Command+2.

Transition Speed

You can also control how fast a transition occurs, by selecting the *Switch > Transition Speed*. Your choices range from *Slowest* to *Fastest*.



Go Button

The Go Button (or Command+G) enables you to make a transition.



Clicking the Go button does nothing when Wirecast is in AutoLive mode. The only exception is that it will update a live shot if you have made changes to it using the Shot Editor. Later in this tutorial you will discover how to use the Go button to transition between different shots when AutoLive is off.

Layers


Note: Before you start this section, please select Smooth as your transition.

STUDIO


Wirecast enables you display several shots in the Preview and Live windows at the same time by rendering them one on top of another according to Wirecast's Layer system. This is an excellent way to add and remove objects in your broadcast.

Wirecast displays five layers in the Main Shot List window. They are numbered 1 through 5 along the right side of the window. Each layer contains shots that can be selected by clicking it. A red LED light indicates that a shot is selected. When a shot is selected it is displayed in the Live Broadcast window. If you select multiple shots (by selecting a shot on more than one layer) they will all be displayed in the Live Broadcast window. The shots are displayed in a layering manner, where layer 1 is on top and layer 5 is at the bottom (and layers 2 through 4 are layered in between).


Select the Logo shot in layer 2 and the River shot in layer 3. The result is a layered shot containing both images.



Layers are displayed in a particular order: Layer 1 is on top, Layer 2 below it, Layer 3 below Layer 2, etc. This tutorial, so far, has been operating on Layer 3. Blank, Ripples, River shots and Movie shot are on Layer 3 (as seen previously in this tutorial), but Layer 2 has only a logo and a blank shot.



Each layer can be turned on or off by clicking the white LED light on the far right side of the layer window. Click the Layer 2 LED to remove the Logo shot.



Click the LED again to turn Layer 2 back on.


Auto Live

So far in this Tutorial, Wirecast has been running in AutoLive mode. What this means is that any change you make in the Shot List is automatically made live in your Broadcast.

This mode is very useful for those users who want to set up all of their shots at once and then single-click them as they run their presentation. But the disadvantage of this single-click method is that you can only see one shot change at a time. Once you click a shot, your viewers also see it (with no preview of how it looks on your part).

Turn AutoLive Off

An LED light, next to the Go button is lit when you are in AutoLive mode.




Make sure AutoLive is off by unchecking *AutoLive* in the Switch menu. A dialog box is shown informing you that AutoLive is off and transitions must be made using the Go button. Click OK in the dialog box to continue.

Try clicking the Ripples and River shots. Nothing happens because AutoLive is off. Now click the Ripples shot and click the Go Button. The Ripples shot is taken live in the Live Broadcast window. Click the River shot and, as expected, nothing happens. Click the Go button again and the River shot becomes Live.

Note: When AutoLive is off, you must always click the Go button (or press the Command+G keys) to display the selected shot in the Live Broadcast Area.

Multiple Changes

The benefit of having AutoLive off is that you can make several changes first and then have them occur all at the same time. To do this, first verify that AutoLive is off. Click *Sample Title* in layer 1, click *Blank Shot* in Layer 2, and click the *Ripples* Shot in Layer 3. Click the Go button (or Command+G) to make the *Ripples* and *Sample Title* shots live at the same time.




Preview

STUDIO


One problem you may have noticed while running this tutorial is that you cannot see the changes you are making before broadcasting them. To solve this problem, Wirecast enables you to see a preview of what you broadcast.

Select *Preview* from the Layout menu. A preview window is displayed to the left of the Live Broadcast window.

Click the River shot on Layer 3. The River shot is displayed in the Preview window. The Preview windows uses a green LED light to identify it. The Live Broadcast window uses a red LED. When shots are selected they display a green or red LED to indicate selection for preview or live broadcast.




Click the Go button to make the River shot live. Click Blank Shot in Layer 1 to remove the title from the ripples shot.



Note: Taking a shot live will set the Master volume slider to the value of the Preview volume slider.

Click the Go button again to make the Ripples Shot live. Notice that the Ripples and River shots LED's have change color because the Preview and Live windows exchanged images. This lets you know what your last live window looked like as you prepare your next shot in the Preview window.

Click Go button again




Tutorial 2: Editing Shots

The first tutorial used only the Main window, and explained various ways in which you can use an existing shot. But shots can also be created and edited. This tutorial demonstrates how to edit your shots.

You create shots for use in broadcast presentations. Shot editing enables you to make shots you need for your broadcast. Shots can be configured in different ways. Some shots have only titles and some just a logo, others may have only a picture. When you broadcast you are choosing -- in real time -- the shot you want to display.

Note: Before you start this tutorial, create a new tutorial document by selecting Create Document Tutorial from the Help menu. You should see a new Main window as shown below.




Shot Editor Overview

Double click the Ripples Shot. This opens the Shot Editor window.

Note: If you save a document with the Shot Editor window open, Wirecast remembers this and re-opens the edit window when the document is re-opened.

The Shot Editor window has three main areas: Shot Preview, Configuration Area, and Source Layers.




Shot Preview This area shows exactly what this shot looks like to your viewers when you take this shot live.

Configuration Area This is where you make changes to the content of the shot, and set its parameters. The configuration area changes appearance depending on the selected Source Layer.

Source Layers This area enables you to add, remove, and reorder the sources in your shot. Sources are ordered visually from top to bottom. For example, the first source in the Source Layer List appears on top of all other sources in the preview. This list also controls visibility of each of the elements in the shot.

Source Layers


The bottom left part of the Shot Editor window lists the sources that make up your shot.




Click on the Logo icon (source) in the Configuration Area. Notice that the Logo is displayed in the Shot Preview area. Click the Ripples icon (source) and the Preview switches to Ripples. This is how you change the source media for this layer in the shot.

Template Window

The Template window icon is located in the controls bar in the middle of the window.




Click on the template window icon to open the Template window. Select the *Angled In* template and click the *Apply* button:




Notice the Preview has changed again in the Shot Editor window, and now shows the Ripples image on the Left side. This is because the template selected has an A and a B

portion to it. Two different sources can be assigned to A and B, but for now only A is assigned (with the Ripples source):



Sources in Wirecast can be assigned either A, B or C in the Source Layers list. To change the assignment, click the A (or B or C) icon and make a selection. This makes choosing a new template much simpler because Wirecast automatically positions the correct sources on screen.


For example, to change the media for the source that is identified as B, select the source identified as B, then click the River icon in the Configuration area. Your Preview should now look like this:




Titles

STUDIO


You can also add a title to a shot. First click the plus (+) button on the bottom of the Source list to add a new layer:




To add a title template, click the T button on the control panel:




Select the title template called *Blue Banner 3* (items are not listed alphabetically) and your preview adds the title:



Next, click the **T** icon in the Attributes bar to enable text editing:




Type text into lines 1 & 2 to display it in the preview window:



Effects/Motion


Positioning Objects

The sources in a shot can be positioned anywhere on the screen. Make sure Blue Banner 3 is selected. Click the *Effects* icon in the Shot Editor.



Though the title element is initially placed in the bottom middle of the Preview screen, it can be moved anywhere. To move the title, click and drag it to a new location. You can

also move the title to an edge, corner, or center by clicking on one of the repositioning buttons in the configuration area:




You can also resize or rotate the title.

To resize the title (while respecting aspect ratio), hold the Command key down while moving the mouse vertically. To resize (independent of the aspect ratio), hold the Command key and the shift key down while moving the mouse vertically and horizontally. The Respect Aspect Ratio checkbox in the configuration area must be unchecked.

To rotate the title, hold down the Option key while moving the mouse vertically and horizontally.

Motion for Objects

All objects (including the title) can have motion assigned to them. Click the Motion tab, to open the Build-In/Build-Out configuration panel:




Motion only occurs during a transition (when you click Go, or click a shot in AutoLive mode). Motion defines how to add (Build-In) or remove (Build-Out) a shot element.

There are two forms of Motion:

- 1. Build In (add)** Build In motion occurs when the shot is added to the Live Broadcast display.
- 2. Build Out (remove)** Build Out motion occurs when the shot is removed from the Live Broadcast display.

Changing Motion Options

Click the menu under Build In in the configuration area and select *From Left*. Also check the *Decelerate In* checkbox:



To see this behavior in action, you must go back to the Main window and trigger the Build In action. To do this, follow these steps:

1. Close the Shot Editor window (optionally) by clicking the X in the corner of the window.
2. In the Main window, make sure Smooth transition is selected.
3. Click on the Blank Shot, then click the Ripples shot (recently edited). Notice that when the Title appears it comes in from the left.

Tutorial 3: Broadcasting

This tutorial demonstrates how to setup and broadcast your Wirecast presentations. You can broadcast to a specific computer (Unicast), multiple viewers (Multicast), or even record your broadcast to disk.

There are two main components for broadcasting your presentation (or saving it to disk): Encoding and Destination.

You need to decide how you are going to encode the broadcast. Encoding is the type of compression used (JPEG, MPEG4, etc.). Wirecast comes configured with many common encoding options. (see [The Encoder Presets Window](#))

A destination for the broadcast must be selected. You can send it to a server for broadcast or save it to disk. Your destination is your Streaming Service.

Streaming

You can stream your broadcast to any streaming service provider you choose. The Broadcast section of this user guide provides details on how to do this for many popular providers. This tutorial will show how to stream to Bambuser.

To stream to Bambuser (as an example), follow these steps:


1. Select *Bambuser* from the Destination menu.
2. Select an encoder.
3. Enter your Bambuser username.
4. After you have entered your username, click *Authenticate* to enter your password and generate the RTMP URL. You only need to do this one time because Wirecast stores the channel information for future streams. The default RTMP port is 1935. You may need to configure your firewall to enable connections on this port.

Note: If you do not have a username and password, you can sign up with Bambuser by clicking the Bambuser icon or by clicking *Sign Up*.


5. Select your Bambuser channel.
6. Optionally, enter a Stream Delay value. This provides a time buffer between your live stream from Wirecast and the actual broadcast itself. You can set the delay from

0 to 999 seconds. However, greater delays require greater memory use. The amount of memory used is displayed when you enter the amount of delay.


7. Click OK.




To stream your presentation, click the *Stream* button at the top of the Main window.



If you have not already selected a destination and logged into it, a dialog box displays. Select a destination, log in when asked to do so, then click OK.



The Stream LED will blink until a connection is made. Once you are connected the LED turns full on and a red box is placed around the Stream button. If you cannot connect an error message will display.



Connection strength bars are displayed on the right. Fewer bars indicates a weaker (slower) connection.



If the connection is ever broken, the green bars are reduced to a single red bar, then immediately a *no connection* icon is displayed in place of the bars.



When the connection recovered, the *no connection* icon is replaced with the green bars.

Click *Stream* again to stop streaming. You can also record your broadcast by clicking *Record*.

Main Window

Introduction

This section describes in detail how to use Wirecast's main window.

Topics


- *Overview*
- *Control/Status Bar*
- *Preview / Live Broadcast Area*
- *Countdown Clock Display*
- *Transition Controls*
- *Shot Tool Menu*
- *Shot Selection Area*
- *Layers*
- *AutoLive*

Overview

Wirecast's main window is comprised of these display areas:


- **Controls/Status Area** The top area with the Stream and Record buttons.
- **Preview/Live Broadcast Area** The large area in the center.
- **Transition Controls** The area with the Transition (Cut and Smooth) and Go buttons.

- **Shot Selection Area** The area displaying the shot icons (available shots).



Control/Status Bar

Control buttons and status information are displayed at the top of the Main window.



Wirecast displays the following controls and statistics:

- **Stream button** Click to begin streaming.
- **Streaming time** This displays how long you have been streaming. This value does not reset when you start/stop the broadcast. It is cumulative. This enables you to save portions of a broadcast to disk and still know the total amount of time.

- **Record Button** Click to begin recording.
- **Recording Time** This displays how long you have been recording. This value does not reset when you start/stop the broadcast. It is cumulative.
- **Gear Icon** This is an Output Settings shortcut. Click to open the Output Settings window. (Same as selecting *Output > Output Settings*).
- **Frames per Second** Displays the broadcast frame rate (FPS).
- **Bitrate** Displays the broadcast bitrate (kilobits per second).
- **CPU usage (percentage)** This displays the current load on your CPU when streaming or recording in percent of usage. The encoder affects the CPU usage more than any other parameter in Wirecast. If this value is high, you should use a different encoder, or modify your encoder settings. If the CPU usage is near 95%, use a lower quality video output to lower the bandwidth.

Note: To avoid decrease in video quality, Wirecast should not be used at CPU usage above 80%. See the Telestream Web site for suggested configurations.

-
- **Connection** This displays the current connection quality. The bars indicate the amount of buffer memory used. High bar count reflects low buffer use (good connection). Low bar count reflects high buffer use (poor connection and in danger of broadcast errors). When one orange bar is displayed, the buffer is full.


Preview / Live Broadcast Area

STUDIO

When you open a new document, if you are not licensed for Studio or Pro, only the Live area displays. The Live area shows what is broadcast to your viewers before the encoding or compression. If you are licensed for Studio or Pro, the Preview window is displayed by default.


When AutoLive is off, you can make several changes without your viewers seeing the change. This is most useful when you are using an engineer to run your broadcast. When you are making changes to your broadcast, you may want to see those changes before broadcasting them. Preview allows you to do this.

To see the preview, select *Preview* from the Layout menu. This sets up the Main Window with the Preview Area on the left and the Live Broadcast Area on the right. Clicking the Go button makes the Ripples shot become Live.



Countdown Clock Display

The Main window displays a countdown clock whenever a video shot is playing. If you have multiple video shots playing, click the gear menu icon to select which shot will be associated with the countdown clock.




Countdown clock

Gear icon

Transition Controls


The transition area is in the middle of the Main Window:



There are two Transition buttons, but each can be configured to present one of many possible transition types. In the image above, the two configured transitions are: Cut and Smooth. Since Smooth is selected (button darkened), any transition executed by clicking Go is a smooth transition.


Changing Transitions

If you click the Cut button, it becomes selected and making it the current transition type:




You always have two different transition types available. You can also select one of the two buttons by pressing Command+1 or 2 keys for the two transition types displayed.

If you click the down-arrow on the right side of either transition button, you can select a new transition to assign to that button.



Transition Speed

The transition speed is set by selecting *Switch > Transition Speed*. There are five settings: Slowest, Slow, Normal, Faster, and Fastest.



Go Button

The Go Button (or Command+G) enables you to make a transition occur at any time.




Clicking the Go button does nothing when Wirecast is in AutoLive mode, except to update a live shot if you have made changes to it using the Shot Editor.

Transition Editing


Some transitions have parameters that can be changed. To edit these parameters, select *Edit Transitions* from any of the three transition button drop-down menus (Cut, Smooth, etc.). Select the transition you wish to edit from the drop-down menu. Modify

the displayed parameters as required. Each transition type has its own set parameters. Click OK when finished.




Shot Tool Menu

The Shot Tool Menu provides a way to open live sources, file sources, the Desktop Presenter program, shot graphics, shot audio, and shot templates. The Shot Tool Menu is the circle to the right of the shot icons.



When you hover over the Shot Tool Menu it displays four menu items. Hover over and click a menu item to open it.



There are four menu items:



Live Sources

Click the Live Sources button to display a list of live sources under the categories: System Device, Web streams, and Scoreboard. When a live source is selected, it is added to the Shot Selection area as a new shot.


Shot Audio

Click the Shot Audio button to add an audio file shot. When selected a dialog window displays enabling you to navigate to and select a file.

Desktop Presenter

To start Desktop Presenter, under the Sources menu select either *New Remote Desktop Presenter* or *New Local Desktop Presenter*. Remote Desktop Presenter presents a desktop from another computer in Wirecast. Local Desktop Presenter allows you to present a portion or all of the desktop of the computer where Wirecast is running.

You can also start DTP (local or remote) from the Shot Tool Menu.




File Sources

Click the *File Sources* button to display a list of file-based source categories: Video Shots, Picture Shots, Music (audio) Shots, or a New (empty) Shot. When selected a file selection dialog window displays enabling you to navigate to and select a file to become a shot. Select Add New Shot to add a new, untitled, generic shot without any file-based resources attached.

Shot Selection Area

The bottom part of the Main Window contains the Shot Selection Area, also called the Shot List.




Shot selection area


The shot icons can be made to display any live activity in the device it represents (cameras, streaming, etc.). See [Performance](#) in the Preferences section.

Changing Shots


Right-click on any shot to display the shot menu.




Change Source Select Change Source to change the source of your shot. Upon selection, a menu of sources will display enabling you to make a selection.




Change Audio Select Change Audio to change the audio of your shot. Upon selection, a menu of audio sources will display enabling you to make a selection.



Change Template Select Change Template to change the template of your shot. Upon selection, a menu of templates will display enabling you to make a selection.



Keyboard Shortcut You can create a keyboard shortcut to any shot. To do this, select *Keyboard Shortcut*, then select a menu number to associate with that shot. After you have selected a menu number, that menu item is checked and the number is displayed in the shot icon.



To take a shot using the assigned hotkey, press the number key assigned to that shot.

You can assign multiple shots to the same menu number as long as they are on different layers. When you use the assigned hotkey all the shots assigned to it will be taken. Selecting a checked menu item will uncheck it and unassign the shot.

Select *Unmap All Keys* to remove all hotkey assignments.

Edit Shot You can edit a shot by double-clicking on it, by right-clicking it and selecting Edit Shot, or by selecting Edit Shot from the Edit menu. You can also edit a shot by selecting it and pressing the Command+E keys.

Rename Shot You can rename a shot by right-clicking it and selecting Rename Shot, or by selecting Rename Shot from the Edit menu. You can also rename a shot by selecting it and pressing the Command+R keys.

Duplicate Shot You can duplicate a shot by right-clicking it and selecting Duplicate Shot, or by selecting Duplicate Shot from the Edit menu. You can also duplicate a shot by selecting it and pressing the Command+D keys.

Delete Shot You can delete a shot by right-clicking it and selecting Delete Shot, or by selecting Delete Shot from the Edit menu. You can also delete a shot by selecting it and pressing the Command+Backspace keys.


Moving a Shot to Another Layer

You can move a shot to another layer by selecting *Move to Layer* from the Edit menu, then selecting the target layer from the drop-down menu. Or, you can right-click the Shot and select *Move to Layer*. You can also drag the shot to a different layer.


When shots are created, they are assigned to a specific layer. They exist on that layer until they are moved or deleted. (See [Layers](#).)

Resizing the Shot Icons

You can resize the shot icons on any layer by clicking the up or down arrow on the left side of the layer window. Click the up arrow to make all the icons larger; click the down arrow to make them smaller. Clicking the down arrow when the shot icons are in their smallest state causes the layer window to become hidden.



To un-hide a layer window, click the side arrow that is displayed.




Layers

STUDIO

Wirecast allows you to put shots on any of five different layers. Layering shots enables Wirecast to merge them together, from back (lowest layer) to front, to form a single visual image during broadcast.

When Wirecast first opens, two of the five layers of shots are displayed. You must scroll down (or expand the window) to see the other three layers.




What is a Layer?

Layers are, by default, named 1 through 5. Layers determine the order when presenting images in the Live Broadcast Area. The Bottom layer (5) is drawn first, then the other layers are added, in order, up to Layer 1. Using multiple layers is a powerful way to show a company logo, a background, or a title, independent from each other.

Changing Layers

To select a layer, click its LED to turn it on (click it again to turn it off). When a layer is selected, the selected shot in that layer is displayed in the Preview/Live Broadcast area. If multiple layers are selected all selected shots are displayed.




Moving a Shot to Another Layer

A shot can be moved to another layer by clicking and dragging the shot from one layer to another within the Main Shot window. When shots are created, they are assigned to a specific layer. They exist on that layer until you move them or delete them.


Layer Zooming

You can zoom in on any layer, enabling you to see the icons more clearly. To do this click the up or down arrow on the left side of the layer window. Click the UP arrow to make all the icons larger (zoom in); click the down arrow to make them smaller (zoom out).

Clicking the down arrow when the shot icons are in their smallest state causes the layer window to become hidden.



To un-hide a layer window, click the side arrow that is displayed.




AutoLive

AutoLive is turned on and off by selecting *Switch > AutoLive* (or by pressing the Command+L keys). When AutoLive is on, changes made in the Shot List are automatically taken Live in the broadcast (using the current transition and duration). If you click a shot when AutoLive is off, the shot is not sent to live broadcast. In this mode you take the shot live manually, by clicking the Go button, or by pressing the Command+G keys.


Live Icons

You can, optionally, make your live source icon display its source (camera, Web stream, etc.) in real time. This means that inside the icon, you will see what the live source sees.



To turn on the *Live Icon* option (on by default), select the *Performance* tab in Preferences, then check the Live Icons checkbox. You can also adjust the frames per second rate of the display using the slider. Lower FPS rates reduce the time taken to

adjust the live icon display. Higher FPS rates provides a smoother display of the live icon source.



Keyboard Shortcuts

Introduction

This section provides a list all of keyboard shortcuts used in Wirecast. They are arranged according to how they appear in the drop-down menus in the main window.

General Shortcuts

Misc Shortcuts	Keyboard Shortcut
Display Shot	<shot number key*>
Spacebar	Left-hand transition button
Enter	Right-hand transition button
i	Sets the media IN point
o	Sets the media OUT point
e	Sets the Replay IN point
r	Creates a Replay shot
=	Increments Home score
-	Decrements Home score
]	Increments Visitor score
[	Decrements Visitor score

* See Keyboard Shortcut in [Changing Shots](#).

WirecastUstream Menu

Wirecast Menu	Keyboard Shortcut
Preferences	command+comma
Hide Wirecast	command+H
Hide Others	control+command+H
Quit Wirecast	command+Q

File Menu

File Menu	Keyboard Shortcut
New	command+N
Open	command+O
Import Media	command+Shft+I
Save	command+S
Save As	command+Shft+S
Close Window	command+W

Edit Menu

Edit Menu	Keyboard Shortcut
Undo	command+Z
Redo	command+Shft+Z
Cut	command+X
Copy	command+C
Paste	command+V
Select All	command+A
Edit Shot	command+E
Rename Shot	command+R
Duplicate Shot	command+D
Delete Shot	command+Delete

Switch Menu

Switch Menu	Keyboard Shortcut
Go	command+G
Cut	command+1
Smooth	command+2
AutoLive	command+L

Media Menu

Media Menu	Keyboard Shortcut
Start Playing All Movies	command+P
Pause All Movies	command+Shft+P
Play to Next Point	command+RightArrow
Jump to Previous Point	command+LeftArrow

Source Menu

Source Menu	Keyboard Shortcut
Show Source Settings	control+command+S

Output Menu

Output Menu	Keyboard Shortcut
Output Settings	command+Y
Start/Stop Broadcasting > Start All	command+B
Start/Stop Recording > Start All	command+K

Layout Menu

Layout Menu	Keyboard Shortcut
Preview	control+command+P
Master Audio	control+command+M
Main Shot List	control+command+L
Go to Layer > Master Layer 1	command+T
Go to Layer > Master Layer 2	command+F
Go to Layer > Master Layer 3	command+N
Go to Layer > Master Layer 4	command+B
Go to Layer > Master Layer 5	command+A

Replay Menu

Replay Menu	Keyboard Shortcut
e	Replay Mark In
r	Create Replay Shot

Social Menu

Social Menu	Keyboard Shortcut
	NO SHORTCUTS

Window Menu

Window Menu	Keyboard Shortcut
Minimize	command+M
Inspector	command+I
Encoder Presets	control+command+E
New Layer Window > Master Layer 1	command+T

Help Menu

Help Menu	Keyboard Shortcut
	NO SHORTCUTS

Adding Media

Introduction

In addition to live video from your cameras, Wirecast enables you to work with media created outside of Wirecast. This section introduces some common media types you can use with Wirecast.

There are three ways to add media to Wirecast:

- 1. Drag & drop into a new shot.** The simplest way to add media to a shot is to drag & drop the media directly into the Shot List in the Main window.
- 2. Drag & drop into an existing shot.** To add media to an existing shot, drag & drop the media directly into the Shot Editor's media list.
- 3. Select directly.** You can add media by selecting Import Media from the File menu, by pressing the Command+Shift+I keys, or by clicking the plus (+) button in the Shot Editor.

Topics

- [Images/Opacity](#)
- [Supported Codecs](#)

Images/Opacity

Wirecast supports a wide variety of still images types (TIFF, GIF, JPEG, PNG, etc.). Some of these formats offer some form of opacity (or transparency). This is often called an Alpha Channel. Wirecast works seamlessly with these formats making them the preferred methods for using graphics and logos, which have transparency.

GIF and Transparency

GIF files are a special case because they only offer transparency and not a true Alpha Channel. The GIF format enables you to define part of the image as transparent (completely invisible), but does not enable you to define it as partially transparent.

Some GIF images use transparency for much of the image. However, near the edges of the visible data, transparency cannot be used. This happens quite often when there is a shadow near the edges of the visible data. The author of the GIF often assumes a certain background color (white, for example) and that color becomes embedded in the actual image.

When Wirecast displays these types of images, the edges of the visible data shows the background that was saved in the GIF. This is not a defect in Wirecast and, therefore, Wirecast can only present the data as it exists in the GIF. The solution is to obtain the original image and re-save the image as either TIFF or PNG. Both of these formats offer full Opacity.

Keynote Movies

Wirecast supports some special features of Keynote Movies which enable you to move back and forth between the pages from within Wirecast. With this feature you can visually annotate and walk through your Keynote for your viewers.

Exporting from Keynote

To take advantage of these features within Wirecast, export the movie into a QuickTime file:

1. Open your presentation in Keynote.
2. Select Export from the File menu.
3. Choose QuickTime and click Next.
4. Choose Interactive Slideshow.
5. Click Export, enter your file name, then click Export again.

Using Movies

To use the movie in Wirecast, follow these steps:

1. Drag & drop the Keynote movie into the Shot List in the Main Window.
2. Click the movie to take it live in the Live Broadcast Window. (Or, if you have AutoLive off, click the Go button.)
3. To go forward in the Keynote movie, select Play to next point from the Media menu (or, press the Command+Right Arrow keys). The Keynote movie plays to the next section using the transition you selected in Keynote.
4. To go backward in the Keynote movie, select Jump to previous point from the Media menu (or, press the Command+Left Arrow keys). All media in the Live area jumps to the previous point.

Windows Media

Windows Media Files (WMV and WMA) are not supported by Wirecast. The solution is to convert the media into a different type, such as MPEG-4.

Real Media

Real Media Files (.RM) are not supported by Wirecast. The solution is to convert the media into a different type such as MPEG-4.

Supported Codecs

Shown below is a list of supported video and audio codecs.

Video Codec	MOV (M4V)	MP3	MPEG-4 ISO (MP4)	WAV	AIFF (AIF)	ASF (WMV)
AVC	YES	NO	YES	NO	NO	NO
H264	YES	NO	YES	NO	NO	NO
DVC25	YES	NO	NO	NO	NO	NO
DVCPRO50	YES	NO	NO	NO	NO	NO
DVCPRO100	YES	NO	NO	NO	NO	NO
MJPEG	YES	NO	NO	NO	NO	NO
ProRes	YES	NO	NO	NO	NO	NO
(mac only)						
Windows Media Video	NO	NO	NO	NO	NO	YES (windows)
Audio Codecs:						
AAC	YES	NO	YES	NO	NO	NO
MP3	YES	YES	NO	NO	NO	NO
PCM	YES	NO	NO	YES	YES	NO
Windows Media Audio	NO	NO	NO	NO	NO	YES (windows)

Titles

Introduction

STUDIO


Wirecast offers a wide variety of title banner templates to use in your broadcast. Adding a professional looking title is as simple as selecting a template and adding your text.

Topics

- [Adding Titles](#)
- [Modifying Titles](#)
- [Title Area](#)
- [Placing Titles](#)
- [Creating New Templates](#)


Adding Titles

To add a title to a shot, double-click the shot to open it in the Shot Editor:




Double-click a shot to edit

Wirecast displays the shot you selected in the Shot Editor window:




Adding New Source

To add a new source, click the plus (+) icon in the Sources Toolbar at the bottom-left corner of the Shot Editor window. Wirecast adds a new source entry, labeled *[no media]*.



Using the tools in the Attributes toolbar and the Media Panel, you can configure your source so it displays as requires:



Configuring Titles


The basic configuration for a media source is a title bar with text captions. Other attributes are optional. As you configure the media, you can view your progress in the Preview area at the top of the Shot Editor window. To configure a title, follow these steps:

1. Select the Change Media icon in the Attributes toolbar. (Each time you create a new source, the media icon is selected for you).
2. Click the T icon in the Media Panel to display titling templates. Scroll through the icons and select the banner graphic you want to use for a title. Be sure to select a title banner that is graphically designed to display the number of lines (1 to 4) you intend to use for this source. Wirecast provides many templates, but you can also create your own.
3. Click on the Visual Effects icon in the Attributes toolbar to adjust the position of the banner, control its opacity and matting, and set other visual effects. Usually, no adjustments are needed.
4. Click on the Crop icon in the Attributes toolbar to crop the banner graphic as needed. As you adjust crop values, you can see the effect in the Preview window.
5. Click the Text icon in the Attributes toolbar and enter up to 4 lines of text to display in the title. You can adjust paragraph formatting, font characteristics, and font color using the buttons to the right of each line.
6. If you plan to chroma key the title, click the Chroma icon in the Attributes toolbar to enable and set up the chroma key. See Shot Editor Chroma Key to learn how to enable and configure chroma key settings.
7. Click on the Motion icon in the Attributes toolbar to set up your builds.
8. Click on the Filters icon in the Attributes toolbar to add and configure filters to use in this title.

Note: For more detailed information on the above steps, see [Edit Menu](#).

Modifying Titles

To modify the titles, you have to edit the shot. Double-click the shot to open the Shot Editor. Click the title attributes tool (T icon) in the Attributes toolbar. The title modification screen displays:



Title Area

Depending on the title source selected, you can modify up to four lines of information. Each line of text has its own justification, font, and font color settings.



Changing Text

To change the text, enter the text into the text entry area for the line to be changed. Wirecast supports all text entry (even in-line entry engines for Japanese, Korean, Chinese, etc.).

Changing Justification

Justification is controlled by clicking on the justification icon and selecting left, center, or right from the drop-down menu.

Changing Font

Click the font selection icon to open a font selection window. Click the icon again to close the font selection window.

The font selection window is a floating palette that changes the text as you make selections. So if you click in a different text entry area, the font panel notices this and configures itself to the settings of the new text entry area.

Note: The only items that Wirecast recognizes in the Font Panel are: Font Family, Typeface, and Size. All other settings are ignored by Wirecast

Changing Font Color

Click the font color icon to change the color of the font. A standard font color selection window is displayed. Choose the color you desire and click OK.

Placing Titles

The previous sections describe how to create and edit a title for an existing shot. However, you can also create a shot which has only title data. This is very useful if you want to place the same title over several different shots or if you want to modify the title independent of the shot you are choosing. But you must decide, based on your type of broadcast, if you want your titles tied directly to specific shots or if you want them to be independent. Wirecast seamlessly supports both methods -- even both methods at the same time.


Seminar Title

You may want to broadcast a seminar and have the title of the seminar appear and disappear while switching between several other shots or cameras. In this case, create a shot which has only the title in it, enabling you to move this title to a Foreground layer. In this configuration, you can bring the title in and out of your broadcast by selecting between a blank shot and the title shot from your foreground master layer. By placing the title in this separate layer, it keeps it independent of the all other shots you have created.

Interview Title

If you are broadcasting an interview, the shot which contains the camera for the interviewee may have a title in it. In this case, when you cut to the shot of the interviewee, the title appears. When you cut to the person asking the questions, the title does not appear because it is a different Wirecast shot.

Note: Since you can turn visibility of a title on and off inside the Shot Editor, you can still turn the title on and off in the shot. To turn it off, make the shot live, then open the Shot Editor. Click the shot icon and then click Go (or press Command+G). To turn it back on, click the shot icon again and click Go.



Creating New Templates

The templates that Wirecast uses are not editable within Wirecast. However, you can create new templates yourself using any graphics creation tool and an XML editor.

Example

Download the example custom templates from Telestream at:
http://www.telestream.net/downloads/Wirecast/titles/Wirecast_User_Titles.zip.

Decompress this file and copy the XML and PNG files to:
~/Library/Preferences/Vara Software/Wirecast_User_Titles.

The next time you launch Wirecast, the user titles will be available. Any media used by these templates must exist in the same template folder. For example, if *user_scoreboard.png* is used in one of the example templates, it must be located in the *Wirecast_User_Titles* directory.

Other Media

Any media used by these templates must exist in the same template folder. For example, if *user_scoreboard.png* is used in one of the example templates, it must be located in the *Wirecast_User_Titles* directory.

Editing XML Files

There is an XML file called *description.xml* which describes all of your titles. Edit it to add, create, or delete titles. Read the header of the XML file for a list of rules and descriptions. Backup the file before editing because syntax errors cause Wirecast not to parse the file.

Logos

Introduction

When you perform a broadcast, you may want to include a company logo in your presentation. There are two ways you can do this in Wirecast:

- 1. Global Logo (logo is its own shot)** In this configuration, you create a shot which has only a logo in it. The benefit of this configuration is that you can show the logo independently of all other shots. For example, you can choose to always show the logo in a corner of your Live Broadcast display.
- 2. Shot Logo (logo is part of another shot)** In this configuration, you add a logo to an existing shot. This is useful if you want to have a shot to use in the start of your broadcast.


Topics

- [Global Logos](#)
- [Shot Logos](#)


Global Logos

Logos are only displayed through shots. Wirecast treats logos the same as any other static media. To create a new empty shot and add your logo to it, follow these steps:


- 1.** On Layer 2 in the Main Shot window, open the Add Shot menu.




2. When the Add Shot menu displays, Select *Add New Shot*.




3. When the New Shot displays, double-click it to edit it.




4. When the Template window displays, select *Fullscreen View* and click *Apply*.




5. Click the *Show Shots* icon and select the logo image to display it in the Shot Preview window:




6. Alternatively, you can click the Add (+) button, select *Add Picture* from the drop-down menu, then select the image you want to use.



7. To resize the logo, make sure the logo shot source is selected, click on the logo in the preview window while pressing the Command key, and drag to resize the logo image.




8. To reposition the Logo, click the *Position* button in the Attributes Toolbar and click one of the positioning arrows:




The logo can also be moved, resized, and rotated using these controls:

- **To Move:** Click and drag object to a new location.
 - **To Resize (maintaining aspect ratio):** Hold the Command key down while moving the mouse vertically.
 - **To Resize (independent of the aspect ratio):** Hold the Command key and the Shift key down while moving the mouse vertically and horizontally. The Respect Aspect Ratio checkbox in the configuration area must be unchecked.
 - **To Rotate:** Hold down the Option key while moving the mouse vertically and horizontally.
9. To add your Logo to the broadcast, close the Shot Edit window, and click New Shot in Layer 2.




Click New Shot

- 10.** Click the Ripples shot in Layer 3. Notice that changing shots does not affect the Logo you put on Layer 2, but it does change the background image.



Turning Layers On and Off


One way that you can use Wirecast is to turn layers on and off. For example, Layer 2 can be turned off and then back on by clicking its white LED on the far right side. This is an effective way to have a logo ready to display.




Shot Logos

You can also create a shot with the logo embedded in it. To do this, follow these steps:


1. Double click a shot to open it in the Shot Editor.



2. Click the *Add Source* button to add a new source:




3. To add your logo click the *Add Shot* button then click the logo icon:



4. Most likely, you will not want to display the logo in the middle of the display. To reposition it, click the *Configure Visual effects* icon to display the positioning controls.


The nine repositioning controls move the logo to the top, bottom, side, corner, or middle of the display:




You can also reposition the logo using the mouse:

- **Move Media** Click and drag using the mouse in the Preview area.
- **Resize Media (Respect Aspect)** Hold the Command key while moving the mouse in the Preview area.
- **Resize Media** Turn off Respect Aspect Ratio. Hold the Shift-Command keys while moving the mouse in the Preview area.
- **Rotate Media** Hold the Option key while moving the mouse in the Preview area. Select between shots in the Main window.

5. To change the size of the logo, select the logo source then hold the Command key while moving the mouse over the logo in the Preview area. To move the logo to the lower-left corner, click the lower-left arrow button.



Close the edit window. Notice that the River shot now has the logo embedded in it.



Shot Editor

Introduction

STUDIO


The Shot Editor is used to view a shot, edit it, or create a new one. This section describes how to use the Shot Editor.

Topics

- [Overview](#)
- [Shot Editor Layout](#)
- [Sources](#)
- [Shot Editor Preview](#)
- [Shot Editor Media Panel](#)
- [Shot Editor Effects](#)
- [Shot Editor Cropping](#)
- [Shot Editor Chroma Key](#)
- [Shot Editor Motion](#)
- [Shot Editor Playback](#)
- [Shot Editor Filter](#)

Overview

To edit a shot, double-click it or right-click and select *Edit Shot*.



The Inspector

You can also edit a shot using the Inspector. The Inspector is opened by selecting Inspector from the Window menu.

When the Inspector opens, if the shot you want to edit is not displayed (or no shot is displayed), single-click a shot in the Main window shot list to open one. The Inspector immediately displays the shot so you can edit it.

Activating Changes

Wirecast always displays your visual changes in the preview panel. However, your changes only become Live when you specifically click Go (or press the Command+G keys).

Note: The exception to this occurs in the Playback Panel where you can specifically make your changes become live.

The AutoLive feature does not apply when using the Shot Editor.


Inspector vs. Editor

A shot can be edited in two ways: You can double-click on the shot and open an editor specifically for that shot, or you can open the Inspector window and then click the shot you want to edit. Both windows display the same set of controls. The only difference is that the Editor window displays a specific shot and the Inspector window displays all the shots that can be edited. Additionally, you can display and edit shots in both the Shot Editor and the Inspector at the same time.

If no shot is currently selected, Inspector buttons and other GUI elements are not functional. To select a shot for editing, single-click a shot in the Shot List panel at the bottom of the Main window.

Shot Editor Layout

The Shot Editor is comprised of four major sections: Preview Area, Source List, Attributes Toolbar, and the Attributes Editor Panel.



The preview area displays a preview of how the shot looks. As you edit a shot by changing its attributes, visual changes are displayed in the Preview area.

The Source List is a list of sources (live sources, images, and title banners) currently in the shot. Wirecast enables you to put up to seven sources in each shot. You add and delete sources by clicking the plus (+) and minus (-) icons in the toolbar at the bottom of the Source List. Click a source in the list to edit it. Sources are layered in the shot, from top to bottom on the list. You can reorder sources using the up and down arrows in the toolbar below the list, or right-click the source and select Move Up or Move Down. (See [Sources](#).)

The Attributes Editor Panel displays each of the configuration panels. At the top is an Attributes toolbar for configuring each category of attributes. To view or edit a given attribute category, click the appropriate icon in the Attribute Toolbar. The attributes change depending on the type of source (live source, graphics, audio, etc.) currently selected.

Sources


Sources are specific resources made available to Wirecast that include configuration settings. These sources can be titles, live camera feeds, graphics, etc., and they are incorporated into shots used in a broadcast. You can place up to seven sources in a shot, where they are placed as layers that reside in front or in back of each other.

Templates


Wirecast also provides pre-built source sets, called templates, which you can add to your source list. Templates are pre-defined configurations used for displaying the sources of a shot. The templates contain place holders, labeled A, B, and C, that define where the sources in a shot are located. For example, you can select a two-source template that displays one element in full-screen and another, superimposed in the bottom left corner. When a different template is selected for the shot, the sources stay the same but their locations are redefined.

Templates provide an easy way to add several sources to a shot, all pre-arranged and organized in popular scale, angle, and position patterns (left/right, stacked, superimposed, etc.). Some templates have a single place-holder, some have two, and still others have three.


To add a set of template-based sources to your shot, click the Add Presets button to the right of the Sources List title.



Wirecast displays a Template window with two tabs: Templates and Virtual Sets. Click the Templates tab and select the template you want to use, then click Apply.




The Preview has changed in the Shot Editor window, and now shows the Ripples image on the Left side. This is because the template selected has an A and a B portion to it. Two different sources can be assigned to A and B:



Sources in Wirecast can be assigned either A, B or C in the Source Layers list. To change the assignment, click the A (or B or C) icon and make a selection. This makes choosing a new template much simpler because Wirecast automatically positions the correct sources on screen.

For example, to change the media for the source that is identified as B, select the source identified as B, then click the River icon in the Configuration area. Your Preview should now look like this:



Virtual Sets

PRO


In Wirecast Pro, you can also add pre-built source sets complete with graphics to simulate a news-anchor desk. These sets are appropriately called virtual sets which can be added to your source list. Virtual sets are predefined sources with graphics, available in various configurations. For example, you can select a two-source virtual set that displays three layers of decor (overhead lighting, a curved desk and a pillared background) with two live sources.

Virtual sets provide you with an easy way to create a professional looking scene with one or more live feed sources superimposed on it. These virtual sets can be used as they are, or they can be edited to suit your needs.


To add a virtual set to your shot, click the *Add Presets* button to the right of the Sources list title.



In the Template Chooser window, select the *Virtual Sets* tab, then click the virtual set you want to use. Click *Apply* to display it in the Shot Editor preview area.



Select a source by clicking on the name of the source in the list.



Controlling Source Visibility

The condition of the icon to the left of each source name controls its visibility. You can hide or display sources in a shot by clicking its icon. When a source is hidden a red X is displayed over the icon.

For example, if your shot has a title, you can turn the title off by clicking once on the icon to display the red X. All of your title data still stays within the shot, but it is just not shown. To turn the title it back on, click the icon again and the red X disappears. This can be a powerful way to use Wirecast by pre-loading your shots with titles and then turn them on and off during your broadcast.


Note: The first time you select a source, its visibility is turned on (Wirecast assumes if you are clicking on it, you want to display it).

Shot Editor Preview

The Preview area displays, in real time, the changes you make to the static video sources in your shot. However, temporal features (fade-in, audio playback, etc.) are not


portrayed in this still shot. You can also click and drag a source displayed in the Preview area, to reposition it.

If you add a Virtual Set, the Preview area displays a zoom slider directly below the preview window. This enables you to adjust all of the layers in the virtual set, to zoom in on the set for a close up or pull back for a wide-angle view.



Shot Editor Media Panel

The Shot Editor Media Panel provides a library of your shots, enabling you to easily assign media to a given source. You can assign three types of media to a source: Live Feeds, Media Files, and Title Banners. The Media Panel displays each category separately, making it easier to categorize and identify your media.



Live Feed Sources

Click the Movie Camera button (camera icon) to display, manage, and select your Live Feed sources. Live feeds also include the devices built into your computer: microphone, Built-in Inputs, and any iSight camera.

To add a live feed to a selected source, follow these steps:

1. Click the movie camera icon in the media panel.
2. Click the Plus (+) icon at the bottom of the media panel and select the system device you want to use for input. Wirecast adds it to the list.
3. Click the configure button (2nd button from right in the toolbar) to configure the device as needed.
4. Click the change media button (far left in the toolbar).
5. Click the Plus (+) icon at the bottom of the media panel, and select Show Source Settings to view and configure source settings.
6. In the Source Settings panel, select the device to display and change settings as needed.
7. Click Apply to save settings and close the Source Settings window.

PRO

In Wirecast Pro, you can add other system devices, including a Scoreboard, and Web streams.

Media File Sources

Click the Media Files button (document icon) to display, manage, and select your file-based media sources. Media files include: video and audio files, video-only files, audio-only files, and raster images (TIFF, JPEG, PNG, etc.). Media files are created outside of Wirecast using media editing tools, then are added to the media list for easy access during broadcasting.

To add media files that you have created (or acquired) to a selected source, follow these steps:

1. Click the Media Files button (document icon) in the media panel.
2. Click the Plus (+) icon at the bottom, and navigate to and select the file you want to add. Wirecast adds this file to the list.
3. Configure it as needed.

Title Banner Sources

Click the Title Banner button (T icon) to display and select a title banner source. Wirecast provides a comprehensive library of one to four line title banners from which you can choose. Title banners are graphic files with text fields that display information you provide. You can not add your own banner files.


To add a title banner to a selected source, follow these steps:

1. Click the Title Banner button (T icon) in the media panel toolbar.
2. Click the Plus (+) icon at the bottom of the media panel and select the title banner file you want to use to title this shot. Wirecast adds this title to the list.
3. Configure the title as needed by entering the text strings for each title line using the Text Attributes tool (4th button from left in the toolbar).

Shot Editor Effects

The Effects Panel enables you to adjust the location of sources and configure opacity, matte, aspect ratio, and scaling as needed. To open the Effects Panel, click the Configure button (2nd button in the toolbar).

Clicking the position buttons (arrows) enables you to quickly change the position of the media in the preview display.




You can also reposition a title using the mouse:

- **To Move Media** Click and drag using the mouse in the Preview area.
- **Resize Respect Aspect** Hold the Command key while moving the mouse in the Preview area.
- **Resize Media** Turn off Respect Aspect Ratio. Hold the Shift-Command keys while moving the mouse in the Preview area.
- **Rotate Media** Hold the Option key while moving the mouse in the Preview area. Select between shots in the Main window

Opacity


The opacity control is a slider bar on the Effects Panel. Opacity controls how much you can see through the media. As an object becomes less opaque, it becomes more transparent

Note: If you want to turn off the media altogether, do not set opacity to zero since this still uses CPU cycles. Instead, you should turn off the visibility of the source.




Matte

A matte is an image that is used to define the opacity of another piece of media. Wirecast comes with several mattes, which are listed in the Matte drop-down menu. Any image in your shot list which has an Alpha Channel also shows up in the Matte menu. (See [Images/Opacity](#) for more information on Alpha Channel.)




Aspect Ratio

The Respect Aspect Ratio is located under the Matte menu on the Effects Panel. When checked, the source retains its aspect ratio when its size is changed. Some sources do not allow you to set this option.




Reposition Buttons

There are three repositioning buttons on the Effects Panel: Reset Position, Scale To Fit, and Horizontal Flip. Click the Reset Position button to reset the media to its original position, size, and rotation. Click Horizontal Flip to mirror the media along the vertical axis. Click *Scale to Fit* button to scale the media to fit inside the Live Broadcast window.




Shot Editor Cropping

The cropping control enables you to cut off unwanted portions of an image. To open the cropping control window, click the cropping control button. There are four sliders and four text boxes used to control cropping. Select an image, then slide the slider until the selected side of the image is cropped as needed. Notice that as the slider is moved, the value in the text box changes. This value is the number of pixels that have been cropped. You can also enter values directly.



Shot Editor Chroma Key

Wirecast enables you to perform real-time Chroma Key operations on your sources during a broadcast. Chroma keying enables you to select a color and replace all occurrences of that color in an image with some other image. Click the Chroma Key button to open the Chroma Key controls. Click the Use Chroma Key checkbox to enable the controls. Use the sliders to set the Key Threshold, Black Clip, and White Clip. Click the Defaults button to restore all controls to their default state.



Working Top Down

The key color is the color of the background you want to drop out of the resulting media. The Chroma Key configuration panel is designed to work through the configuration as a process, from top to bottom, fine tuning your key as you go. It is important to not over-adjust any one control. A good key color is obtained by finding the right balance in the controls.

Selecting a Key Color

To get the best key possible, select the key color using the mouse. To do this check the Pick key color with mouse checkbox. Use the mouse to click a point on the image in the preview area. As you do this watch the preview change in level of transparency, displaying the gray/white checkerboard pattern on the affected regions. Usually, clicking near the corners of the media provides the best key, but sometimes clicking near the main subject in the image is best.

Key Threshold

Once you have the best key by picking the color, you can adjust the key threshold to drop out the background as completely as possible. The Key Threshold parameter enables Wirecast to determine how close the color in the video is to the key color. Adjust the key threshold (0 to 100) by using the slider.

Black Clip

Sometimes, dark areas are keyed out, when they should not be, due to how digital cameras function. The Black Clip parameter controls how close the keying is toward black. For example, if the host has black hair, you need to increase this value slightly so that the keying effect is not seen in his hair. Adjust the Black Clip (0 to 100) by using the slider.

White Clip

Likewise, white areas are also sometimes keyed out when they should not be. The White Clip parameter controls how close the keying is toward white. For example, if the host has a white shirt on, you need to increase this value slightly so that the keying effect is not seen in his shirt. Adjust the White Clip (0 to 100) by using the slider.

Getting a Good Key

Probably the most important part of getting a good key is getting good source material. Poor source material generates poor keys; no algorithm can make up for this.

Lighting

Assuming you have a reasonably good camera, the most important part of getting a good key is good lighting. Invest in good lights and learn how to set them up properly. Here are some basics:

- The background screen (green or blue) needs to be independently lit from other items in the shot.
- Light the background screen evenly, with no shadows. The more evenly lit, the better the keying.

- Light people evenly with no shadows. A fill light is very important. An office white board may be helpful in accomplishing this.


Good Camera

You should get reasonable quality out of most cameras on the market today. Wirecast has been tested with a low-end DV camera to verify the quality of its Chroma Keying system. However, the better the camera the better the keying.

If you use a cheap USB Web-cam, it may not give you enough source quality to get a reasonably good key. But if you have excellent lighting, an iSight camera works well. 3CCD is better than 1CCD. If you have the choice, a PAL camera is better than NTSC, due to how data is captured internally.

High Quality Video


If you are keying video from disk and not capturing it live, make sure the High Quality Video option is checked in the Advanced Preferences Panel. This forces Wirecast to decode the video from disk in the best quality possible, giving the Chroma Key the best data possible for keying. Wirecast warns you if High Quality Video is turned off when you turn on Chroma Keying.



Shot Editor Motion

The Motion Panel provides control over how objects (image, movie, title, etc.) are added or removed in the Live Broadcast window. To open the Motion Panel, click the Motion Panel button in the Toolbar. Wirecast only performs motion during a Smooth transition. If you are using any other transition, the motion settings are ignored.

There are two types of motion. When an object is added to your broadcast it is called Build In; When it is removed it is called Build Out.



Motion only occurs when an object enters or leaves the Live Broadcast window. For example, if you have two shots, each with a foreground and the media in the foreground is the same, then a Smooth transition is performed between the foregrounds. However, no motion is performed. Or, if a logo is positioned in the top left corner in an existing shot, and it is in the bottom right corner in a new shot, when you make the new shot Live the logo smoothly transitions from the top left corner to the bottom right corner. But the Build In and Build Out settings are ignored.

However, if you have two shots with a Foreground, but the media in each is different, the Build Out is performed for the existing shot, and the Build In is performed for the new shot.

Direction Menus These provide selections of where the Build In comes from (top, bottom, right, etc.) when it is added, and where the Build Out goes when it is removed.

Fade In / Fade Out Checking these checkboxes causes an object to be added or removed gradually. If unchecked, the object is instantly added or removed, much like a cut transition.

Spin In / Spin Out Checking these checkboxes causes an object to be added or removed in a spinning fashion.


Scale In / Scale Out Checking these checkboxes causes an object to be added or removed in a scaled fashion.

Decelerate In / Accelerate Out Checking these checkboxes causes all of the above actions to be performed at a slower or faster rate.

Apply To All Click this button to make the Motion Settings the same for all sources in a shot. This is useful if you want to make all of your motion the same for all of the elements in the shot.

Shot Editor Playback

The Playback Panel enables you to control how movies and music play in Wirecast. To open the Playback Panel, click the Playback Panel button.



Check the Live Playback checkbox to cause your changes to be taken live in your broadcast. The four control buttons enable you to rewind, play, pause, or fast forward. In Point & Out Point sets the start and stop points in the media.

Select a playback speed for your shot. The audio is muted for any speed other than normal.

Select what to do when the media is finished (loop, hold, or remove) from the drop-down menu. Check the Begin Playing checkbox to cause the media to automatically start playing when it becomes live. Check the Remember Position checkbox to cause the media to remember its position when it is not live.

The vertical slider sets the audio level and the two meters display it in stereo (left and right). Click the Master Audio Mute icon to mute the audio of your broadcast. Click it again to un-mute it.

The Playback Panel only allows modification of parameters on media for which the options are possible. For example, if your media has no audio, then the audio controls are not active. Or, if your media is a still image, you are not able to set an In Point or Out Point nor play the image.

The Playback Panel setup information is saved separately for each shot, so if a media is used in two different shots, the media settings are different in each shot.

Live Playback

Live Playback is a part of the Playback settings. By default, changes in the Playback Panel are like any other changes in the Shot Editor, they do not take effect until you click the Go button. However, there are times when you may want to scrub (slowly scroll and view) the video and see the scrubbing in the Live Broadcast window.

☒ Live Playback : Changes are live


Check the Live Playback checkbox to cause changes you make in the Playback Panel to become live. This gives you immediate control over the movie or audio in your broadcast.

Note: If you want to pause all movies in your broadcast, you can select *Pause All Movies* from the Media menu. This is particularly useful if you only have just one movie and you want to quickly pause it.

Scrubbing


The Scrubbing slider enables you scrub (scan) back and forth through your media. The triangle icon in the scrubbing slider is called the playhead.

Click and drag this triangle (playhead) left and right to view any location in your media. The primary use of scrubbing is to set the In Point and Out Point in your media. If Live Playback is checked, and the shot you are editing is live, then the scrubbing is also seen in your broadcast.



Transport Controls


The Transport controls enable you to Rewind, Play, Pause, and Fast Forward. If Live Playback is checked, any changes you make using these controls are seen in your broadcast.



In and Out Points

The In Point and Out Point controls are a part of the Playback settings. The In Point is the position in the media where playback starts. For example, if you set the In Point of a movie to 2 seconds, when the movie starts to play (or loops back to the start), it starts from the 2 second point in the movie. The Out Point is the position in the media where playback ends. if you set the Out Point of a movie to 5 minutes, when the movie reaches the 5 minute mark, it stops playing (or loop back to the beginning, depending on which When Finished option you have selected).

To set the In Point, move the playhead to a place you want the media to start playing and click the first Set button. To set the Out Point, move the playhead to the place you want the media to stop playing and click the second Set button. Clicking a Jump button moves the playhead to the In Point or Out Point location.



When Finished Control

The When Finished drop-down menu enables you to control what happens when the media finishes playing (when it reaches the Out Point).

You have three options:

- **Loop** The media loops back to the In Point.
- **Hold** The media stops and displays the last frame.
- **Remove** The media is removed from Live Broadcast Area. The remove function makes the media transparent after it is done playing. For example, if you are doing a live show with an intro video layered over your camera feed, when the intro video is finished it becomes transparent, leaving only the camera feed displayed.

Note: For media without video, the Hold and Remove are effectively the same option.



Begin Playing Control

When checked, the Begin Playing checkbox causes the media to start playing when the shot becomes Live. Checked is the default.




Remember Position Control

If the Remember Position checkbox is checked, when a live shot transitions to another shot with different media, the removed shot remembers the last position where the media was played. And so, if the removed shot becomes live again it starts playing from that remembered position. Checked is the default.

☒ Remember position even when not Live

Audio Controls

If a piece of media contains audio, the audio controls become activated. The audio in each media is independently controlled. The audio slider bar enables you to control the media audio level. Clicking the speaker icon mutes the audio of your media in the Live Broadcast. Clicking it again causes it to be heard. The stereo audio meters monitor the audio output level.




Shot Editor Filter

The Filter Panel is available when you are editing a shot and you have selected one of the following sources: Title, Foreground, Scene, or Background.

Note: Filters are only available for Macintosh OS X 10.4 (Tiger) or greater.


To add a filter, click the plus (+) button at the bottom of the Shot Edit window and select a filter from the drop-down menu. In the example below, the Color Controls filter has been added to change the colors in the shot.



Modifying the Filter Parameters

A filter can have a large number of parameters. Therefore, it is beyond the scope of this user guide to describe all of the possible options a particular filter may provide. However, the parameters should be straightforward to configure, using the controls provided.

Here is an example of changing the contrast on the River image:



Source Settings

Introduction

These topics describe how to use the Source Settings editor.

Topics

- *Overview*
- *System Devices*
- *Scoreboards*
- *Teradek Cube*
- *Remote Desktop Presenter*
- *Local Desktop Presenter*
- *Wirecast Cam*
- *Web Stream*
- *Capture Cards*
- *Show USB Devices*


Overview

To open the Source Settings window, select *Sources > Show Source Settings*.

Note: Since some of the Source Menu items are plug-ins, the order of the items will not always be the same.

The Source Settings window is divided into four sections: System Devices, Preview Window, Configuration Area, and Button Bar:

- The System Devices displays all the devices detected by Wirecast (USB and FireWire devices, microphones, line inputs, Webcams, etc.). Sources used are selected from this list.
- The Preview Window provides a preview of the video coming from a selected source.
- The Configuration Area is for configuring sources. When a source is selected from the System Devices list, the configuration options for that source are displayed.
- The Button Bar contains two buttons. Click the plus (+) button to manually add new sources. Click the minus (-) button to remove them.




Note: In Wirecast versions 4.0 and above, de-interlacing has been moved from System Preferences (where it was a global setting) to the Source Settings, where it is individually controlled by each device.


System Devices

System devices include Firewire devices, USB cameras, and other USB devices. Click on a device to select it. Two drop-down menus and a configuration button are displayed. The *Capture Device Size* menu selects the device resolution from 160x120 to 1920x1080, depending on the camera. The *Device Deinterlacing* menu selects either None or Blend. None turns off deinterlacing enabling the video to interlace normally. Blend

turns deinterlacing on enabling the video to avoid interlacing problems during motion. Click **Configure** to configure the selected device.



When you click *Configure*, a properties window displays with two tabs. The *Video Proc Amp* tab enables you to set the video display properties. The *Camera Control* tab enables you to set camera image properties. Any properties that do not apply to the selected camera are greyed-out.




Scoreboards

PRO

Scoreboards allow you to add a scoreboard graphic to your broadcast that can be dynamically updated. To add a new scoreboard, select **New Scoreboard** from the Sources menu. Multiple scoreboards can be added.

When a scoreboard is opened in the Source Settings editor, it displays a preview of the scoreboard, two drop-down menus, and two configuration tabs.



Unlike most other elements in Wirecast, changes to the Scoreboard go live instantly without requiring a transition. Once the scoreboard is live, the preview image is exactly as it is seen in your broadcast.

Of the two drop-down menus, the first selects the style of the scoreboard (Pipe, Shade, Corner, Wide, etc.) and the second selects the scoreboard layout (Basic, Top, Bottom, etc.). Some layouts change the number of fields surrounding the scoreboard, allowing additional live information to be added.

There are four hotkeys associated with the Scoreboard.

=	Increments Home score
-	Decrements Home score
]	Increments Visitor score
[	Decrements Visitor score


In order for these hotkeys to be active, the scoreboard must be displayed in the Live window and the Wirecast main window must be in focus (selected as the active Windows window).

The Data Tab

The Data tab configures the information displayed inside your scoreboard. The first two lines of data hold the name and score of each team. Before broadcasting, you should enter the names of each team here. While the broadcast is live, click the “+1”, “+2” and “+3” buttons to modify the score.

There are also four information fields (Field 1 through 4). Each field controls a line of text inside the scoreboard that can be seen using the various layout types.

Note: Because Wirecast updates the scoreboards dynamically, It is recommended that you fill in the additional information fields while using a layout that hides them. Then, change to a layout that reveals those fields when ready, otherwise your viewers see you typing in those fields live.




The Look Tab

The Look tab controls the visual elements of your scoreboard. In the Name Options column, there are three buttons for each field. These buttons enable you to change the text alignment, font style and text color respectively. The Score Options (on the right side) provide the same three adjustments to the score.


Some scoreboard styles also allow you to change the background colors of the Home and Visitor fields, to make them match their team color. This option, when displayed, is located between Name Options and Score Options.

You can also choose a custom image as the background of your Scoreboard. To do this check *Use Custom Image*. When you do, the Choose button is enabled. Click *Choose* and navigate to your custom background and select it.



Teradek Cube

You can download the Teradek plugin from: <http://www.teradek.com/pages/downloads>. On the download page, select *StreamReader Plugin for Wirecast*.




STUDIO

Remote Desktop Presenter

The Remote Desktop Presenter (RDTP) is a utility application that enables Wirecast to broadcast the desktop of any computer running the Telestream Desktop Presenter program.

Desktop Presenter is normally auto-detected by Wirecast and is automatically added to the list of sources. However, if a RDTP is not detected, or if you want to add one in a remote location you can manually add it by selecting *New Remote Desktop Presenter* from the Source menu in the Main window.

You can then setup the presenter in the Source Settings window by entering an IP address of the target computer, optionally checking the With Audio checkbox, and clicking Apply:




Note: When a Desktop Presenter has been auto-detected, the IP Address field is disabled.

For more information, refer to the Telestream Desktop Presenter User Guide.


Local Desktop Presenter

The Local Desktop Presenter (LDTP) is a utility application that enables Wirecast to broadcast the desktop of your computer running Wirecast. It enables you to capture from a local source at high resolution and at a high frame rate. It can be used to capture video sources. Add a LDTP by selecting *New Local Desktop Presenter* from the Source menu in the Main window.


Setup the presenter in the Source Settings window by selecting a Capture Type: Monitor or Window. *Monitor* captures the whole display from a specified monitor. *Window* captures any selected window.



Click *Select Window/Monitor* (above) to define what monitor or window to capture. If you selected *Monitor* for the *Capture Type* (above), you can choose which monitor to capture, if you have multiple displays.



If you selected *Window* for the *Capture Type*, a selection window opens. Select an Application, then select a Window (only windows associated with the selected application are listed) to identify which window is captured.



Other Local Desktop Presenter controls are:

Show Cursor When checked, causes the cursor to be captured in addition to the video source.

Capture Audio When checked, captures audio in addition to video. Click Audio Settings to select the audio source.

FPS Select the frame rate at which you want the video to be captured.

Disable Capture When checked, capture is disabled.

Audio Settings Enables you to select an audio source to be captured with the video.

Sources are automatically detected and displayed in the Web Stream list. They are also identified as *ONVIF* or *Bonjour* detection. Select also an ONVIF Profile. Set controls as needed, then click *Connect* when finished.

The screenshot displays the 'Source Settings' window for a 'Local Desktop Presenter'. The interface is divided into several sections:

- SYSTEM DEVICES:** Lists 'Built-in Digital Input Audio' and 'Built-in Line Input Audio'.
- CAPTURE CARDS:** Lists 'DeckLink SDI_1' and 'DeckLink SDI_2'.
- IP CAMERAS:** Lists '2 Linksys WVC80N'.
- PIPELINES:** Lists 'Lab-Quad1-CH2' and 'Lab-Quad1-CH3'.
- WEB STREAM:** Lists several sources, including 'AXIS 211W - 00408CA1DEA', 'AXIS M1104' (highlighted), 'AXIS M1104 - Bonjour H.26', 'AXIS P1344', and 'AXIS P1344 - Bonjour H.26'.

Annotations on the right side of the window provide guidance:

- Select a Web Stream source:** Points to the 'AXIS M1104' entry in the 'WEB STREAM' list.
- Set ONVIF Profile:** Points to the 'ONVIF Profile' dropdown menu, which is currently set to 'quality h264'.
- Set Controls:** Points to the 'Protocol', 'Stream Options', and 'Format Options' dropdown menus.
- Click Connect:** Points to the 'Connect' button at the bottom of the settings panel.
- Detection identifiers:** Points to the bottom of the 'WEB STREAM' list, where sources are identified as 'ONVIF' or 'Bonjour'.

The settings panel on the right includes the following fields and controls:

- Discovery Method:** ONVIF (Open Network Video Interface Forum)
- Username:** root
- ONVIF Profile:** quality h264
- Protocol:** (dropdown)
- Stream Options:** (dropdown)
- Format Options:** (dropdown)
- Ignore Stream Timestamps:** (checkbox, unchecked)
- Live Stream:** (checkbox, checked)
- URI:** rtsp://10.0.5.244/onvif-media/med
- Video Attributes:** h264 - 800x600 (4:3) @ 29.9506fps
- Audio Attributes:** none - 0hz 0 bit signed integer none
- Bitrate:** 1.927 Mbits/sec
- Video:** 1.927 Mbits/sec
- Audio:** 0.000 bits/sec


At the bottom of the settings panel are three buttons: 'Stream Authentication...', 'Connect', and 'Save Settings'.

Wirecast Cam

The Wirecast Cam option allows you to use an iOS device (iPhone, iPad, etc.) as a remote camera. You need only to download the Wirecast Cam app from the Apple App Store and make sure your iOS device is on the same network as your Wirecast computer. When you do this, your iOS device shows up as a *source* in Wirecast.

Wirecast Cam App

Here is how the Wirecast Cam app appears on your iOS device (in this example, an iPhone).




When you open the Wirecast Cam app, a splash screen displays briefly.



Wirecast Cam Dashboard

Here is the dashboard of the Wirecast Cam app. There are five buttons, a time/bitrate display, and a resolution/framerate display.



Time/Bitrate display Displays the time duration of your broadcast. The clock is reset each time you start your broadcast by clicking the Start/Stop button. Displays also the bitrate of your broadcast and is displayed only while broadcasting.

Microphone button Turns the microphone on and off. When off, the icon has a line through it.

Settings button Displays the settings for Wirecast Cam (See [Wirecast Cam Settings](#)).

Start/Stop button Starts and stops your broadcast. When on, the button is square. When off, it is round.


Switch Camera button Switches between front and back camera. When back camera is selected, the icon does not change.

Light button Turns the iOS device light on or off. Only the back camera has a light. This button is only displayed when the iOS device has a back side camera.

Resolution/Framerate Displays the current resolution and framerate settings. These are always displayed, even when not broadcasting.

Wirecast Cam Settings

Click the Settings button to display the Wirecast settings menu. Setup the Wirecast Cam as needed for your broadcast, and click Done when finished.



Resolution Click to set the resolution of your camera. This value is displayed in the lower left-hand corner of the Wirecast Cam app. It is always displayed.

Audio Turns the audio for your broadcast on or off. Audio is on when green is displayed.

Key Frame Interval Serves as a reference for other frames in your broadcast. (See the description provided in the Settings menu).

Bitrates Click to set the bitrate of your broadcast. The bitrate is displayed in the upper left-hand corner of the Wirecast Cam app. It is only displayed while you are broadcasting.

IP Address Displays the IP Address of your iOS device.

About Wirecast Cam Click to display version and copyright information about the Wirecast Cam app.


Starting Your Wirecast Cam Broadcast

Once you have set up the Wirecast Cam app for your broadcast, select a camera (front or back, turn on the microphone and light as needed, then click the Start button. Your

Wirecast Cam is now ready to be detected by Wirecast on your PC connected to the same network as your iOS device.


Adding a Wirecast Cam Source

Once the Wirecast Cam app is started (and is on the same network as your Wirecast PC), Wirecast detects the presence of Wirecast Cam as a source and makes it available on the Add Sources menu. To add Wirecast Cam as a source, select an iOS device from the Add Sources menu.




Note: If the iOS device is not automatically detected you can also manually add the iOS device by selecting *Sources > New Wirecast Cam* and manually enter the IP address of the iOS device.

After you have added a Wirecast Cam, a Wirecast Cam shot is created. Double-click the shot to make settings and connect to the Wirecast Cam.




When the Source Settings window displays, set (optionally) the latency to *Low* or *Normal*, then click *Connect*. Your Wirecast Cam image will display in the viewer window at the top.



Your Wirecast Cam will be automatically detected by Bonjour and placed in the list or sources that can be added.

After you close the Source Settings window, you can click the Wirecast Cam shot to place it in the Preview window. Click the Go button to take your Wirecast Cam shot live.



Web Stream

PRO

The Web Stream option allows RTMP, RTSP, MMS, or HTTP streams to be taken directly into Wirecast. This is useful for incorporating remote IP Cameras or other network streams into a broadcast.

Select a Web Stream source. Sources are automatically detected and displayed in the Web Stream list. They are also identified as *ONVIF* or *Bonjour* detection. Select also an ONVIF Profile. Set controls as needed, then click *Connect* when finished.

The screenshot shows the Wirecast Web Stream configuration window. On the left, a sidebar lists system devices, capture cards, IP cameras, and pipelines. Under the 'WEB STREAM' section, several sources are listed, including 'AXIS M1104'. A line from the annotation 'Detection identifiers' points to this list. The main panel displays the configuration for the selected source. At the top, a video preview shows a forest scene. Below it, the 'Discovery Method' is set to 'ONVIF (Open Network Video Interface Forum)'. The 'Username' is 'root'. The 'ONVIF Profile' is set to 'quality h264', with a line from the annotation 'Set ONVIF Profile' pointing to it. Below this are dropdown menus for 'Protocol', 'Stream Options', and 'Format Options', with a line from the annotation 'Set Controls' pointing to them. There are checkboxes for 'Ignore Stream Timestamps' (unchecked) and 'Live Stream' (checked). The 'URI' field contains 'rtsp://10.0.5.244/onvif-media/med'. Below the URI, video and audio attributes are displayed: 'Video Attributes: h264 - 800x600 (4:3) @ 29.9506fps' and 'Audio Attributes: none - 0hz 0 bit signed integer none'. Bitrate information is shown at the bottom: 'Bitrate: 1.927 Mbits/sec', 'Video: 1.927 Mbits/sec', and 'Audio: 0.000 bits/sec'. At the bottom of the main panel are three buttons: 'Stream Authentication...', 'Connect' (with a line from the annotation 'Click Connect' pointing to it), and 'Save Settings'. A vertical scrollbar is on the right side of the main panel.

The Web Stream controls are:

Protocol Select the protocol to use with your incoming stream.

Stream Options Select a set of options based on the protocol you selected (the sub-protocol of the stream). RTSP can be transmitted over UDP, TCP, or HTTP. RTMP can be transmitted non-encrypted, over http, encrypted. If unsure what to use, select *Auto Detect*.


Format Options Select a video format to use for transcoding. If you select *Auto Detect* (the default) Wirecast will automatically detect the format to use from the incoming stream.

Ignore Stream Timestamp When checked, stream timestamps are ignored. Every Audio/Video frame has a Presentation timestamp, a time that tells the player when to show the frame. Checking this box causes the Web Stream to ignore the presentation timestamp set by the video stream and just use the current system clock.

Live Stream When checked, specifies that the stream is a live stream and video on demand. For Wowza servers, it does not do anything, but for Adobe Media Servers, Live Stream must be checked for live streams.

URI Enter the address of your input stream. (For example: *rtsp://127.0.0.1:8080/my_stream.sdp*, or *http://10.0.0.1/my_stream*, or *rtmp://hades.telestream.net:1935/live/myStream*).

ONVIF Authentication Click to connect to remote devices, like IP cameras, which require login credentials for access. Check the *Remember* checkbox to save your credentials to cause the device to automatically connect.




Save Settings Click to save your Web Service control settings.

Capture Cards

STUDIO

Capture Cards are hardware extensions that enable you to bring in video from more advanced HDMI and SDI sources. Most capture cards are automatically configured to the best settings. Some cards (Blackmagic Intensity Pro, for example) require some manual adjustments. When a Capture Card is selected, you can select the Frame Format. Clicking Save causes the video to display. You can also check the De-interlacing checkbox to turn on de-interlacing. Once configured, you can add Capture Cards from the Live Source drop-down menu in the Main window.

If you experience difficulty with your Capture Card, make sure you have the latest driver from the vendor and that it is installed correctly before contacting Customer Support.



Capture cards supported by Wirecast:

- Blackmagic Intensity Pro
- Blackmagic Intensity Shuttle
- Blackmagic Decklink Studio
- Blackmagic Decklink SDI
- Blackmagic Decklink Duo
- Blackmagic Decklink Extreme 3D
- Osprey 240e, 450e, 700e
- Matrox Multi


Blackmagic

PRO


You can use Blackmagic cards to send live feeds directly into editing, effects, and broadcast design systems. In order to use this feature, install a Blackmagic card with

associated drivers, then restart Wirecast. The Blackmagic card will then be listed in the Output menu.


Under the Output menu, select a Blackmagic card, and then select an HD setting for its output. If your card has multiple outputs, you can select more than one and they will output simultaneously at independent resolutions and frame rates.



To begin outputting, select *Start Output*. If you have multiple outputs selected they will all begin outputting.




You can stop the Blackmagic card output by selecting *Stop Output*. If you have multiple outputs selected they will all stop outputting.



Show USB Devices

To view a list of all USB devices select *Show USB Devices* from the *Sources* menu. The list displays all connected USB devices, the USB bus on which each USB device is located, and the speed of the device. This information is helpful when troubleshooting USB bus bandwidth issues. Click *Show All Devices* to display all available USB devices, otherwise only video devices are listed. Click *Refresh* to update the list.



Playlist

Introduction


Playlist enables you to create a list of clips and play them as a single group. You can have multiple playlists and edit them as needed after they are created. You can also replay playlists (see [Replay](#)). This makes the combination of Playlist and Replay a very powerful production tool.

Topics


- *[Creating a Playlist](#)*
- *[Adding Clips](#)*
- *[Playing Playlists](#)*
- *[Playlist Controls](#)*
- *[Restoring Playlist Position](#)*
- *[Countdown Clock Options](#)*

Creating a Playlist

To create a new Playlist, select New Playlist Shot from the Shot Menu and a new Playlist shot icon is added in the shot window.




The Playlist shot icon displays a playlist badge, the playlist duration, and the playlist completion action.



Adding Clips


To add clips to the playlist, first click and drag them onto the layer where the new Playlist is located.




Second, click and drag each shot onto the playlist icon. When you do this you must wait for the playlist icon to obtain a yellow border before releasing the click button.



Double-click the Playlist icon to open the Playlist window. You can drag and drop more clip directly into the Playlist window when it is open. You can also add clips by selecting Add New Shot from the Shot Menu.




These added shots are now housed in the Playlist. You can still edit shots in the playlist by double-clicking on the shot. You also have all of the Change Shot menu options available by right-clicking on the shot.




Note: Do not delete shots from a playlist while the playlist is live.

The Change Shot menu for Playlist shots has one additional option: Modify Duration. You can set the shot duration to any value by selecting *Modify Duration* and entering a new duration when the dialog box displays. Click OK when finished.




You can, optionally, reset the duration to its original value by clicking *Reset*.

You can also add live sources to the playlist. To do this click the Live Sources menu and select a live source from the list.




By default, live sources have an infinite duration (since they are not a clip). So, you must assign a duration by selecting *Modify Duration* for the live source and entering a duration when the dialog box displays. Click OK when finished.



Note: Wirecast does not support nested playlists (playlists withing playlists).

Playing Playlists

Playing back a playlist is the same as playing any other shot -- click the playlist shot to place it into preview, then click the Go button to take it live.




Click Playlist icon

Click the Go button

Playlist runs in live window

Playlist Controls

Playlist provides some basic playback controls. You can transition to the previous or next shot in the list, set playlist behavior, transition between shots, and choose the currently live shot.



Transition to previous shot

Transition to next shot

Set Playlist behavior


Transition between shots

Make selected shot live

Transition to previous shot Transitions to the previous shot in the playlist if the playlist is currently live.


Transition to next shot Transitions to the previous shot in the playlist if the playlist is currently live.

Set Playlist behavior Sets the behavior of the playlist when the last shot in the list has been played. A check mark indicates what menu item (behavior) is selected.



- *Loop* transitions back to the first shot, endlessly.
- *Hold* stays on the last shot. If the last shot is a clip, the last frame in the clip is displayed. If the last shot is a live shot, the live source stays active.
- *Available Shots* transitions to another shot on the same layer. All available shots are listed as menu selections. (In the example shown, the only available shot is "Logo".)
- *Previous Live Shot* transitions back to the shot that was live before the playlist began playing.
- *Current Preview* transitions the contents of Preview to the live window.


Transition between shots Sets the transition to use between shots in the list.



Make selected shot live Takes the currently selected shot in the playlist live, if the playlist is live.

Restoring Playlist Position


Checking the *Restore Previous Active Shot* check box causes the playlist to remember which shot was playing (and its position) when the playlist is taken live.




Without checking the *Restore Previous Active Shot*, the playlist always starts from the first shot.

Countdown Clock Options


Select *New Playlist -- Completion* from the gear menu (displayed only when playlist is playing) to display the countdown clock for both the current shot playing in the playlist as well as the countdown for the playlist itself. When *New Playlist -- Completion* is not selected (not checked) only the current shot countdown clock is displayed.



Add a live source to your playlist by selecting a live source from the Shot Source menu.



When a live source is in a playlist, a *New Playlist -- Live* option is added to the playlist gear menu. When you select this option, the countdown clock displays the time remaining until the next live source in the playlist begins to play.



The countdown time until the next live shot is the sum of the durations of all the shots preceding it. When the live shot begins, the countdown clock displays the countdown of that live shot. If the live shot does not have a duration, then the playlist is halted and the live shot remains until another shot is taken live or the playlist is replayed.

Social Media

Introduction


Social Media enables you to add social media messages to you broadcast and you can filter what messages are displayed. The only social media available in Wirecast is Twitter.

Topics

- *Settings*
- *Message Feed*
- *Create Shot*

Settings

The first thing you need to do is log on to Twitter. To do this click *Social > Settings*, select Feed Type, enter your login information, and click OK.




A screenshot of a Twitter login dialog box. The dialog box contains four input fields: 'Username:', 'Password:', 'Feed Type:' (a dropdown menu showing 'Home Timeline'), and 'Search String:'. At the bottom are 'OK' and 'Cancel' buttons. Four lines with labels point to these elements: 'Enter login info' points to the Username field, 'Select Feed Type' points to the Feed Type dropdown, 'Click OK' points to the OK button, and an unlabeled line points to the Password field.


Field/Label	Description
Username:	Enter login info
Password:	
Feed Type: Home Timeline	Select Feed Type
Search String:	
OK	Click OK
Cancel	

Message Feed

Click *Social > Message Feed* to add some Twitter messages to your broadcast. When the message window displays, search (optionally) for the messages you want to broadcast.




To select messages to be rotated in your broadcast, first check *Rotate Selected Every*, and enter the number of seconds of the rotation interval. Select the messages you want rotated by checking the box at the left of each message. Select a starting message.



You can also (optionally) check *Auto Refresh* and enter number of seconds. The gear icon allows you to select or unselect all messages. Once you have selected your messages, close the Message Feed window.

Create Shot

To create a new Social Media shot, select *Social > Create Shot*. When the new shot icon is displayed, click it to place it in the Preview window. Then click the Go button to take it live.



Replay

Introduction

PRO

Replay enables you to repeatedly play a clip, or even a portion of a clip, any number of times or endlessly. You can also replay playlists (see [Playlist](#)). This makes the combination of Playlist and Replay a very powerful production tool.


Note: Multiple Replay clips captured during the same replay session will not render correctly when played at the same time on different master layers or different shot layers.

Topics

- [Replay Settings](#)
- [Replay Activation](#)
- [Replay Templates](#)

Replay Settings

To use Replay you need to set it up the way you want it to perform. To do this select *Replay > Settings*. Make your desired settings and click OK when finished.



Video Quality Set the video quality for Standard or High. Depending on what quality you choose, an estimate of the *write rate* will be displayed.

Audio Check the Audio box to capture audio in the Replay you are creating. If unchecked all audio is ignored.

Maximum Duration Sets the maximum duration of the Replay buffer. *Unlimited* allows you to go all the way back to the beginning of your broadcast (no matter how long), which will require a lot of disk space, or you can select *Limited to* which allows you to choose how many minutes back into your broadcast is buffered. This option uses less disk space. Depending on how many minutes you choose, an estimate of the *disk storage required* will be displayed.

Note: If you set maximum Duration to Unlimited Replay will use disk space until all available is used.

Replay Folder Click Browse and navigate to the location where you want to store your Replay shots.

Default Replay Duration Specifies the default duration of a Replay clip (sets In and Out points) when you click *Create Replay Shot*. For example, when the duration is set to 30 seconds (the default value) it means that the In point will be set 30 seconds before the Replay shot was created.

Create Replays In Allows replays to be created in master layers or playlists. You can still move the shots to other layers at any time after they are created.

After Creating Replay Shot When checked, the Replay shot is displayed in the Preview window. This allows you to set the In and Out points for the Replay shot rather than having to open the shot editor to set them.

Activate Replay On You can choose to start the buffering of Replay (activate the Replay system) manually, when you start recording, or when you start broadcasting. The problem with *Manually* is that you may forget to turn on the buffering. So *Record* and *Broadcast* options are provided to allow this to be automatic.


When Deleting Replay Shot When deleting a shot, you can choose to have Wirecast ask (prompt) you if you want to keep recording, or just to keep recording without asking you, or to just delete the recording.

Replay Shot Template Allows you to select an existing Replay shot to act as a template for other Replay shots, or no template at all (by choosing *None*). For more information see [Replay Templates](#).

Use As Defaults Click this button to make all the settings you have made to be the default used in all created Replay shots.

Replay Activation


To activate Replay, select *Replay > Activate*. When you do this, the Activate menu item becomes *Deactivate* and several new buttons are added to the Wirecast main window: Set Replay Endpoint and Create Replay Shot (same as selecting *Replay > Create Replay Shot*).




Once Replay has been activated it keeps all shot activity (playing of clips or capturing of live sources) in the Replay buffer on disk. The amount that is saved when the *Create Replay Shot* button is pressed depends on what value was entered into the *Default Replay duration* setting.

Start playing a clip (while Replay is activated), then click the *Create Replay Shot* button. Since the Default Replay Duration is set at 30 seconds, a Replay shot of 30 seconds (backward from when the Create Replays Shot button was pressed) is created. The new


Replay Shot is placed in Layer 1 (as designated in the settings) as an icon and the Replay controls are displayed at the bottom of the Preview window.



Now that you have a 30-second Replay Shot displayed in the Preview window, you can use the controls to set the Replay In and Out points and then take the Replay Shot live by clicking the Go button.




The Endpoint button allows you to tighten up your Replay capture. When Replay is active, it captures all past activity of your source (clip or live source) into the buffer. But you can shorten how much of the capture you actually get in a Replay shot by clicking the Endpoint button first (to establish when to start your Replay Shot, and then click the *Create Replay Shot* button when you are finished with your Replay shot. Your Replay Shot now has just the content you wanted.




Another control available at the bottom of the Preview window is the Magnification control. Click the magnifier icon (spyglass) to display a magnification slider. Slide the


slider to the left for lower magnification of the In and Out controls, and to the right for greater magnification.



For example, if you move the slider to the right, the In and Out controls move farther apart, increasing the magnification, so that you can more easily adjust the location of the In and Out controls. This is very helpful when you have long duration Replay shots. However, the slider will quit sliding when you have reached the maximum size of the Replay Shot.




One more control is available at the bottom of the Preview window. It is the Replay the speed control. You can set the speed of the Replay Shot by clicking the speed icon ("1x") and selecting a speed from the pull-down menu. Your choices are 1x (normal speed), 2x (double speed), .5x (half speed, and .25x (one-fourth speed). The audio is muted for any speed other than normal.




Replay Templates

Replay templates allow you to create a template shot to use as a pattern for how you want your Replay Shots to look and act.


Create a new shot, then double-click that shot to open it in the shot editor. When the Template Chooser displays, select the Fullscreen View template and click Apply.




When the Shot Editor opens, add another layer by clicking the Add (plus) button in the lower left corner. Open the Clip Sources menu and select an image for the new layer. Close the Shot Editor when finished.




Right-click the new shot and select *Rename Shot*. When the Rename Shot window opens, rename the shot Replay Template. Click OK when finished.




Open Replay Settings (*Replay > Replay Settings*) and select *Replay Template* from the *Replay Shot Templates* menu. Click OK when finished.



There is also a Replay Channel menu. From here you select which channel (layer) in the template shot to use in the Replay Shot. You can only choose one channel (A, B, or C). This channel (layer) is replaced by the video playing when the Replay shot is created. Any other channels (layers) that exist in the template shot are used exactly as they are (content, size, and position) in the Replay shot.



You are now ready to create a Replay Shot using the Replay Shot template. To do this, activate Replay by selecting *Replay > Activate*. Start playing a video in the live window, then click the *Create Replay Shot* button. This will create a new Replay shot that used the template to add the logo image on another layer. The new shot has an icon in the shot area and is opened in the Preview window ready for you to set In and Out points and to take live by clicking the Go button.



Audio Inspector

Introduction

PRO

The Audio Inspector enables you to monitor and control all of the audio sources from a single control panel. This section describes in detail how to use the Audio inspector.

Topics

- *Overview*
- *Hardware Audio*
- *Shot Audio*

Overview


To open the Audio Inspector panel, select Audio Inspector from the window menu.

PRO

Note: The use of the Audio Inspector requires a Wirecast Pro license. For licensing information, select Preferences from the Wirecast menu, click the Add (+) button, then click Purchase. Or, contact sales@telestream.net.

The Audio Inspector separates your audio by hardware and shot. Live Input is always the first section to the right of the Master control, and it contains all hardware audio sources you may be using. This includes microphones, audio input feeds, cameras,

capture cards, Web streams, etc. The remaining audio controls are associated with specific shots.




Hardware Audio and Shot Audio

The Master control sets and displays the total audio output of your broadcast. Click the headphones icon (directly below the Master controls) to mute the local audio feed. (This has no effect on the broadcast audio output.) The Mute button, below the headphones icon, mutes all local audio and all broadcast audio.


Below the name of each audio source is a white label box. You can rename this box to describe your source. To rename the audio source, click in the white box and enter the new name.

Hardware audio sources are automatically added to the Audio Inspector whenever a new audio source is added through the Main window or through the Shot Editor. You can also manually add a hardware audio source by clicking the Live Input drop-down menu at the top of the Live Input section.



Hardware Audio

Hardware audio sources are hardware devices and live sources. This includes dedicated microphones, cameras (that have audio), audio line feeds, capture cards, etc.



When you add a device to the Audio Inspector as a Live Input, it defaults to the lowest volume level, because all Live Input audio sources act as global audio sources through the Audio Inspector. Thus, any source listed in the Live Inputs section can be immediately added to a broadcast by dragging the volume slider on that source up.

The horizontal slider in a Live Input controls the audio delay. Dragging the slider to the right increases delay, up to one second, to fine-tune audio in sources where the audio is ahead of the video.

Note: Audio that is out of sync with video is common when running a microphone directly into your computer's audio input when using a FireWire camera as a video source. Most FireWire devices create a latency that causes the audio to be ahead of the video.

Shot Audio

Shot audio sources come from shots that are currently live in your Wirecast document. Any time a shot becomes live, it immediately displays in your Audio Inspector.

Adding Shot Audio Sources

The Shot Audio panels are always displayed to the right of the Live Input panel in the Audio Inspector. Shot audio is automatically added to your broadcast whenever a shot containing audio transitions to live broadcast.

New Shot Audio controls are created as multiple shots are made live during the broadcast. For example, if you have live shots with audio sources in Master Layer 1, 2 and 3, Wirecast displays three Shot Audio panels. Each panel enables you to control the audio output of the source it controls.

Managing Audio Sources

Shot audio is most useful in controlling the audio levels during a live broadcast. You can use the sliding meters to adjust the volume levels of any source during broadcast. If a source begins contributing audio that is wrong or distorted, you can click the Mute button at any time to silence it. Its muted state is maintained even if you change shots and come back to it.

Preferences

Introduction


Wirecast is designed so that you can configure most of your options directly in your Wirecast document or the Shot Editor. The Preferences window enables you to set up Wirecast, set Desktop Presenter options, manage your licenses, update your software, and set advanced video options.

Topics

- [Accessing Preferences](#)
- [General](#)
- [Performance](#)
- [Licenses](#)
- [Software Update](#)
- [Advanced](#)

Accessing Preferences

To open the Preferences window, select Preferences from the Wirecast menu (or press the Command+ Comma (",") keys). Preferences are grouped under five topics: General, Performance, Licenses, Software Update, and Advanced. Click one of these topics to view and change its preferences.



Wirecast automatically saves your preferences every time you make a change. The changes are immediately applied.

Resetting Preferences

To reset your preferences, quit Wirecast and then delete the files located at:

~/Library/Preferences/Vara Software/Wirecast Preferences.


-

Or, you can use Support Assistant to reset preferences (see *Send Support Information* under [Help Menu](#)).

Note: You should match the output to the canvas size as close as possible to preserve video resolution and quality. For example, a 800x600 source results in significant loss of quality if an aspect ratio of 640x480 is selected. Using 720x576, which is much closer in size, helps preserve video quality.

General

General preferences enable you to setup the Wirecast environment.



Open Last Document on Startup


When checked, the last document you used is opened when Wirecast starts up.

Shot Editor Checkerboard

When checked, a checkerboard background displays in the Shot Editor to indicate an area that is transparent. Checked is the default.

Feedback Detection

When checked, the computer audio is disabled (live feed is unaffected) whenever feedback is detected. Checked is the default. When feedback is detected, the following warning is displayed with an option to turn off feedback detection:



Maximum Reconnection Attempts

Enter the number of times you want Wirecast to try to reconnect to a host provider. The default is three.

Performance

Performance preferences enable you to select the display rate used for all internal video rendering.

You can set the Video Display Rate to 25, 30, 50 or 60 fps. If using PAL sources, choosing 25 may eliminate dropped or duplicate frames. It is recommended that you set this frame rate to match the frame rate of your output video encoder.


You can turn on the Live Icons feature, which makes all icons in the Shot Area display any live activity in the device it represent (cameras, streaming, etc.). You can also set the FPS of the Live Icon display using the slide bar control.



Note: If you are streaming at 60 fps for games, you need to set the video display rate at 60 fps here in Preferences and at 60 fps also in your encoder preset.

Licenses

Licenses preferences enable you to register and license Wirecast. To purchase a license, click *Purchase*. To activate a license, click the plus (+) button.



Serial Numbers

The table in the Buy Upgrade Preference window displays the products and serial numbers that you have received for Wirecast.

Note: The serial number is always composed of numbers and upper case letters (excluding upper case letter O), but it never contains quotation marks. When you receive a serial number, it may be enclosed in quotation marks (e.g., "123-456-789").

To add a valid serial number, press the plus (+) button. If you wish to purchase a serial number from the web store, click *Purchase*. When Wirecast displays the Enter Serial Number window, enter the serial number and click OK. Wirecast validates the serial number and unlocks Wirecast. If you previously purchased a copy of Wirecast and want to use that serial number, enter that serial number to unlock Wirecast.


Note: If you do not want to purchase a serial number directly in Wirecast, you can also purchase a serial number at www.teletstream.net, or you can purchase a serial number from Teletstream by phone at: 530.470.1300.

Manual Activation

If your computer is not on the Internet, you can use another computer to activate your license and unlock Wirecast. To manually activate your license, download the Manual Activation Guide at: www.telestream.net/telestream-support/wire-cast/support.htm and follow the steps in the guide to unlock Wirecast.

Deactivate Serial Numbers

Deactivating a serial number allows you to re-activate it on another computer. You can always reactivate a serial number by re-entering it. To deactivate a serial number, select an activated product serial number, and click *dash icon* (-). Wirecast deactivates the serial number and adds water-marking to the video and audio whenever licensed features are used. When you deactivate a serial number, it is removed from the table.




Demonstration Mode

When no serial number is entered or activated, Wirecast water-marks all output (both to disk and network). The video water-mark is a periodic overlay of the Wirecast logo. Audio water-mark is a periodic voice over. If you have a Wirecast serial number and are using a Wirecast Pro feature without a Pro license, that output is also water-marked.

Software Update

Software update preferences enable you to obtain Wirecast updates.



Automatically Check Updates

Check the Automatically Check For Updates checkbox to cause Wirecast to check for updates on the Telestream Web site each time Wirecast is launched. No personal information is transferred to Telestream during this action.

Check Now

Click *Check Now* to immediately check for updates on the Telestream Web site (www.telestream.net). No personal information is transferred to Telestream during this action.

Advanced

Advanced preferences enable you adjust advanced settings for Wirecast.



Note: Capture Device Size has been moved to the Source Settings window.

Use High Quality Video

Check the Use High Quality Video checkbox to increase the quality of decoding performed on your source media files. If CPU usage is near 95%, or if the frames per second (FPS) is consistently well below your target, uncheck *Use High Quality Video* to remedy this. Checked is the default.

YUV Colorspace

If *Render using YUV colorspace* is checked, video frames will be rendered on the GPU using YUV rather than RGB. This will typically provide a performance advantage and save on memory. Performance will improve when streaming to most destinations (including Virtual Camera Out). The best way to know if this option is advantageous to use on your system is by trial and error, and observe the results.

Disable ONVIF IP Camera Discovery

Check *Disable ONVIF IP Camera Discovery* to turn off automatic discovery of ONVIF IP Cameras.

Disable Bonjour IP Camera Discovery

Check *Disable Bonjour IP Camera Discovery* to turn off automatic discovery of sources using Bonjour.

Asset Manager

Introduction

The Asset Manager is used to change the sources of media in your document.

Topics

- *Documents*
- *Re-assigning Media*

Documents

Wirecast stores a path to your media in the Wirecast document. If you relocate your media, Wirecast no longer is able to find them. In this case, use the Asset Manager to reassign the new media locations. However, Wirecast does keep track of the relative path to your media. If you move both the document and media to a new position, Wirecast still finds the media.

Re-assigning Media


To reassign media, follow these steps:

1. To open the Asset Manager, select *Show Asset Manager* from the Wirecast Media menu.
2. Select the media you want to assign to another source.
3. Some media assets (i.e cameras) enable you to set the aspect ratio by displaying a Device Aspect Ratio menu. You can select an aspect ratio from this menu.
4. Select the new media from the *Assign To* menu, or click Browse and locate the replacement media on disk.

Note: When Desktop Presenter is selected as the source, you can enter the IP address for the Desktop Presenter. This enables you to build a Wirecast presentation with place-holders and then reconfigure at a later date to accommodate a new presenter

with a new Desktop Presenter as a source. Additionally, if you select a camera input source from the Media List, an additional menu to set the Device Aspect Ratio of the camera is displayed. This is useful if the image aspect ratio of your camera is not automatically picked up by Wirecast. In this case, select the correct aspect ratio from the menu, click Apply, then click the corresponding icon in the Shot Selection.

5. Click *Apply* to replace the existing media, then close the Reassign Media window.



Menus and Windows

Introduction

These topics describe the menus, menu items, and keyboard short-cuts in Wirecast.

Topics

- [Wirecast Menu](#)
- [File Menu](#)
- [Edit Menu](#)
- [Switch Menu](#)
- [Media Menu](#)
- [Sources Menu](#)
- [Output Menu](#)
- [Layout Menu](#)
- [Replay Menu](#)
- [Social Menu](#)
- [Window Menu](#)
- [Help Menu](#)

Wirecast Menu

About Wirecast Displays the version you are running.

Preferences Opens the Preferences window. If the Preferences window is already open, it becomes the active window.

Services Presents the Macintosh Services available.

Hide Wirecast Hides all of the windows.

Hide Others Hides all non-application windows.

Quit Wirecast Closes all documents and exits. If the broadcast is playing, you are asked to stop the broadcast first. If a document has not been saved, you are asked to save it.

File Menu

New Creates a new, empty Wirecast document.

Open Displays the Open dialog window for opening a Wirecast document.

Open Recent Displays up to fifteen of the most recently accessed documents. Every time a document is opened or saved it is entered into this list.

Import Media Enables you to import media into Wirecast. A new shot is automatically created using the new media.

Save Saves the document. If the document has not already been saved, the Save As... dialog window is displayed.

Note: Wirecast auto-saves your stream/recording every 20 seconds.

Save As Displays the Save As... dialog window so that the document can be saved using a new file name.

Close Window Closes the currently active Wirecast window. If the window is a document, all of its Shot Editor windows are closed as well. If Wirecast is still broadcasting, you are asked to stop the broadcast. If the document has not been saved, you are asked to save the document before closing.

Edit Menu

Undo Reverses your last change in Wirecast. Undo is only available in some windows (such as the Shot Editor). Wirecast offers an unlimited number of undo actions (within computer memory limitations). Undo information is stored on a per-window basis. Also, if you close a window then reopen it, your undo information is lost.

Redo Reverses your last undo action. Redo is only available in some windows (such as the Shot Editor). Wirecast offers an unlimited number of redo actions (within computer memory limitations). Redo information is stored on a per-window basis. Also, if you close a window then reopen it, your redo information is lost.

STUDIO

Edit Shot Opens the Shot Editor. (See [Shot Editor](#)). You can also double-click a shot, or right-click and select Edit Shot, to open the Shot Editor. The Inspector window is a Shot Editor window which always edits the last touched shot. (See [Inspector vs. Editor](#).)

Rename Shot Enables you to rename a shot. You can also right-click a shot and select Rename Shot.

Duplicate Shot Duplicates the currently selected shot. You can also right-click a shot and select Duplicate Shot.

Add Shot Creates a new empty shot. You can also right-click a shot and select Add Shot.

Delete Shot Deletes the currently selected shot. You can also right-click a shot and select Delete Shot.

STUDIO

Move To Layer Moves a shot to the selected layer. When shots are created, they are assigned to a specific layer. They exist on that layer until they are moved or deleted. You can also click and drag a shot to another layer.

Start Dictation Starts dictation action.

Special Characters Displays the Apple Special Characters interface.

Switch Menu

Go Performs a transition (same action as clicking the Go button).

Transitions Wirecast has two transition buttons that can be assigned any transitions (cut, smooth, etc.) that Wirecast supports. The Switch menu lists the currently assigned transitions by name. These three transitions can also be selected by pressing the control key and either the 1 or 2 key. (See [Transition Controls](#) to modify which transitions appear in this menu.)

Transition Speed Enables you to select one of five transition speeds ranging from Slowest to Fastest.

AutoLive Toggles (turns on and off) the AutoLive feature. AutoLive is a fundamental feature of Wirecast which enables you to control how you make shots become part of the live broadcast. (See [AutoLive](#).)

Live/Preview Swap Toggles (turns on and off) the Live/Preview Swap feature. When on, the Live Broadcast and Preview windows trade panes (swap) when the Go button is clicked.

Media Menu

Start Playing All Movies Starts playing any movies that are not currently playing.

Pause All Movies Pauses all movies that are currently playing.

Show Asset Manager Displays devices that can be configured. Some devices (cameras, etc.) may be configurable. For example, you can configure an iSight camera to manually change its focus, contrast, brightness, etc. Other devices have multiple inputs you can choose (AlchemyTV Card, etc.). (See [Asset Manager](#).)

Note: The Configure Devices menu selection is present only if a device is connected to Wirecast. The configuration user interface is provided by the device maker. It is beyond the scope of this document to describe all of the features available for all devices. See the documentation provided with your device on how to configure it.

Sources Menu

PRO

New Scoreboard Opens the Source Settings window with a new (untitled) Scoreboard selected as a source. Configure the settings and click Apply to create the new source.

New Remote Desktop Presenter Opens the Source Settings window with a new Desktop Presenter selected as a source. Enter the IP address and check *With Audio* to include audio from the desktop. Click Apply to create the new source.

If Bonjour is not installed on the computer running Desktop Presenter, you may need to manually enter the TCP/IP address of that computer. If you want to add a Desktop Presenter before it is available you can use this menu option to pre-configure your document. You can also change the IP address to a Desktop Presenter in the Asset Manager dialog.

PRO

New Web Stream Opens the Source Settings window with a new (untitled) WebStream selected as a source. Enter your user name and click Authenticate.

New Local Desktop Presenter Opens a new local Desktop Presenter. This enables you to present the whole computer display, or any selected window.

New Wirecast Cam Allows you to use an iOS device (iPhone, iPad, etc.) as a remote camera.

Show Source Settings Opens the Source Settings window. (See [Source Settings](#) for more detailed information on setting sources.)

Show USB Devices Opens a list of all USB devices.

Note: Since some of the Source Menu items are plug-ins, the order of the items will not always be the same.

Output Menu

Output Settings Opens the Output Settings window.

Start/Stop Broadcasting Starts (or stops) broadcasting to the network. You can also click the Broadcast button on the Window Bar in the Main Window.

Start/Stop Recording Starts (or stops) recording to disk. If you have not yet configured the Output Settings for this document, you are prompted to do so. You can also click the Record button on the Window Bar in the Main Window.

STUDIO

External Display Output Selects an external display for the output of Wirecast. For example, if you have a projector connected to your computer using S-Video, select it from this menu to display the output of Wirecast to the projector.

If you have a dual-head graphics card, you can select the second monitor to display Wirecast Output. However, if you have two graphics cards, Wirecast may not be able to display to any devices (monitors) on the second graphics card.

Virtual Camera Out Enables you to present the output of Wirecast as if it were a camera (a virtual camera), allowing it to be automatically detected by other applications when they are launched.

Canvas Size Sets the canvas size aspect ratio used when broadcasting a Wirecast document.

Note: You should match the output to the canvas size as close as possible to preserve video resolution and quality. For example, a 800x600 source results in significant loss of quality if an aspect ratio of 640x480 is selected. Using 720x576, which is much closer in size, helps preserve video quality.

Layout Menu

STUDIO

Preview Shows (or hides) the Preview area in the Main window. You can also click the Preview icon in the Main window tool bar.

Master Audio Shows (or hides) the Master Audio controls.

Main Shot List Shows (or hides) the Main Shot List.

Go to Layer Displays the selected layer. You can also press command + Shift keys with the T, F, N, B, or A keys to select a layer. Each of these letter keys represents a layer name: Title, Foreground, Normal, Background, and Audio.

Replay Menu

Activate Activates the Create Replay Shot system. When activated, the menu item becomes *Deactivate*. Click *Deactivate* to deactivate the Create Replay Shot system.

Replay Mark In Allows you to tighten up your Replay Shot capture. Select Replay Mark In to mark the beginning point of your Replay Shot capture.

Create Replay Shot Captures a Replay Shot. The duration of the shot is set in the Replay Settings.

Settings Displays the Replay Shot settings window.


For more information about Replay Shots see [Replay](#).

Social Menu

Message Feed Brings up the Social Media dialog.

Create Shot Creates a shot with a social media title in Master Layer 1.

Settings Brings up the Social Media Settings dialog.



Rotate Messages: Enter the number of seconds that messages rotate into the title.

Refresh Messages: You can choose to manually refresh your message list, or have it automatically refreshed at the rate you enter (in seconds).

Use Account: You can choose to receive messages from Facebook, Twitter, or both.

Window Menu

Minimize Minimizes the front-most window.

Zoom Maximizes the front-most window (zooms to the full size of the screen).

STUDIO

Inspector Opens the Inspector window. There is only one Inspector window for each document. The Inspector is very similar to the Shot Editor, except it always edits the last shot touched.

STUDIO

Encoder Presets Opens the Encoder Presets window.

PRO


Audio Inspector Opens the Audio Inspector window.

STUDIO

New Layer Window Opens a new Master Layer window for the layer selected.

STUDIO

Camera Preview Shows a preview of all cameras currently connected to your computer. Click the *Add Camera* button to add a camera to the preview window. Use the *Adjust FPS* (frames per second) slider to adjust how realistically the camera image responds to motion. (Keep in mind that the greater the FPS the greater the processing power required to render the preview.) Use the *Adjust Size* slider to change the size of the camera image. You can also right-click on any camera preview source and select *Remove*.



Document Windows All open document windows are listed at the bottom of this menu.

Help Menu

Search Enables you to search the help system for any topic or key word.

Wirecast Help Opens the online help version of the User Guide.

Open Wirecast PDF User Guide Opens the PDF version of the User Guide.

Open Tutorial HTML Opens the Wirecast Tutorial in your browser. To follow the tutorial, you'll need to Create a Document for the Tutorial as well.


Create Document for Tutorial Creates a new Wirecast Document which contains the media necessary for following the Tutorial.

Buy/Upgrade Opens *Buy Upgrade* in the Preferences window. This window allows you to purchase licenses and to activate or deactivate them.

Provide Feedback Opens the Telestream Website feedback page where you can enter any feedback you may have about our product or company.

Send Support Information Opens a Support Assistant dialog window. To create a new support ticket, select *Create a support ticket*. The information is sent to the Telestream support team for evaluation. If you have been previously issued a case number, select *Link with existing support case #* and enter your case number. You can also select *Do not receive follow-up from Telestream*. This enables you to send support information to Telestream without receiving a response. Click *Save Report* to save the information to a file on your computer. Click *Send Report* to send the information to Telestream.

Note: You must click *Send Report* to create a ticket. If you click *Save Report*, a ticket will not be created.



The screenshot shows a 'Support Assistant' dialog box. At the top, it has a title bar and a 'Contact Information' section. This section contains three radio buttons: 'Create support ticket and receive followup from Telestream support' (which is selected), 'Do not check if you receive your support directly from a dealer.', and 'Link with existing support case #' (which is followed by a text input field). Below these is another radio button, 'Do not receive followup from Telestream'. Underneath the radio buttons are four text input fields: 'E-Mail Address:' (marked as '* Required'), 'First Name:', 'Last Name:', and 'Company:'. Below these fields is a large text area labeled 'Description and/or steps to reproduce'. At the bottom of the dialog are three buttons: 'Reset Preferences', 'Save Report', and 'Send Report'.

Visit Telestream Web Site Opens the Telestream Website home page.

Visit Wirecast / Desktop Presenter Download Page Opens the Telestream Website download page for Desktop Presenter.

Acknowledgments Opens an on-line help to acknowledgments.

Broadcasting

Introduction

Note: Wirecast will not prevent your computer from entering sleep mode. Therefore, to ensure uninterrupted streaming, you should disable sleep mode on your computer while using Wirecast.


Note: To avoid a decrease in video quality, Wirecast should not be used at CPU usage above 80%. See the Telestream Web site for suggested configurations.

Topics

- *Canvas Size*
- *Virtual Camera*
- *Configuring Output Settings*
- *Configuration*
- *Encoder Presets*
- *Flash RTMP Server*
- *Flash RTMP Server*
- *Flash To Akamai*
- *Flash To Microsoft Azure, Brightcove, Limelight, Sermon.net*
- *Flash To Bambuser, Churchstreaming.tv, DaCast Streaming Services, High School Cube, iNK Barrel Video, Livebeats, make.tv, Meridix Sports Network, Netbriefings, ShowCaster, Streaming Media Hosting, StreamVu, Stretch Internet, Sunday Streams, Tulix, Ustream*
- *Flash To Microsoft Azure, Brightcove, Limelight, Sermon.net*
- *Flash To YouTube*
- *Flash To Zixi*
- *Streaming*
- *Record To Disk*


Canvas Size

The first menu item in the Output menu is Canvas Size. When *Output > Canvas Size* is selected, a drop-down menu with various canvas sizes is displayed allowing you to select the canvas size you want. You can also select *Auto*. This automatically sets the canvas size to the highest resolution that was selected when the encoder was chosen.



Note: Canvas size selection *1080p Anamorphic (1440x1080)* is a narrower (1440) display stretched to display as 1080.

There is also a *Custom* option that enables you to set the canvas width and height.




Wirecast can manage a wide variety of input sources, enabling you to have several live camera sources. However, really high-quality video sources can cause more harm than good. For example, an HD camera feed into a Wirecast canvas that is set to HD resolution and then broadcast out in HD, requires a lot of work for the graphics processor. If the frame rate starts to drop but the CPU usage stays steady, it creates a bottleneck. The solution is to reduce the frame size going through Wirecast. Therefore, there is no need to bring input video in at HD resolution if Wirecast is streaming out a lower resolution.

Keep in mind that resizing down is good but resizing up reduces quality. As a rule, you should try to keep your resolution as constant as possible from source to output. There is no benefit from using an HD camera if you're only broadcasting a low resolution stream. This only increases the work your computer must do without any increase in output quality.

Virtual Camera

Wirecast enables you to present the output of Wirecast as if it were a camera (a virtual camera), allowing it to be automatically detected by other applications when they are launched. To setup Wirecast as a virtual camera, select *Output > Virtual Camera Out*, then select the output resolution to use. You can also select *Match Canvas* to cause the resolution to be the same as the current canvas size.



Once you have selected an output resolution, select *Start* to make Wirecast output available to other applications on your computer.

Some of the applications Wirecast can work with using virtual camera are:

- Google+ Hangouts
- Skype
- GoToMeeting

Note: Virtual Camera only works with one application at a time.

The Virtual Camera menu also provides two additional options: *DirectShow Audio* and *Virtual Microphone*.

DirectShow Audio When selected, outputs DirectShow audio.


Virtual Microphone When selected, enables you to present the output of Wirecast as if it were a microphone (a virtual microphone), allowing it to be automatically detected by other applications when they are launched.

Note: After selecting Virtual Microphone, you must re-start Wirecast to enable Virtual it's operation.


Note: Virtual Microphone can only be installed during Wirecast installation.

Configuring Output Settings


To configure output settings select *Output > Output Settings* (or press the Command+Y keys). When the dialog box displays, select a destination and click OK to open the Output Settings window.



You can also click *More* to display a list of all available destinations. Check the checkbox for each destination you want to include in the destination menu list.



The Output Settings window displays the destination you selected. Each destination window has a unique set of controls including a way to authenticate your connection.



Name: Not Configured

Destination: Bambuser More...

Encoding: H.264 1080p 16:9 (1920x1080) [Gear Icon]

Username: [Field] Authenticate

Channel: [Field]

[Green Square with 'b' Logo] Sign Up

Bitrate: 4242 k

Location: [Field]

Stream Delay: 0 seconds

Multiple Output Settings

Wirecast enables you to specify many output settings for your presentation. This means you may configure Wirecast to broadcast multiple data rates simultaneously, or even broadcast and record with different encoders at the same time. You can also broadcast to multiple Flash destinations while recording to disk.

At the top of the Output Settings window is a list of the current settings. Uncheck the checkbox of any setting you want removed from your broadcast. You can add as many output settings as you need, but keep in mind that each additional destination will require more system resources.

Click the Gear icon to access actions that enable you to create reference movies you can distribute to your viewers. Each destination type provides a unique set of actions.

Configuration


There are two items to configure before broadcasting: Destination and Encoding.

When you broadcast with Wirecast, you must pre-configure at least one destination. A destination can be a broadcast server, content distribution network or local disk recording.


The *Encoder* determines how your presentation is encoded (or compressed). There are many options available. Wirecast simplifies this process by providing several simple presets to choose from. (See also [The Encoder Presets Window](#)).

Encoder Presets


The Encoder menu is located near the top of the Output Settings window. The Destination menu is located above the Encoder menu. The More button and Gear menu provide optional settings.




More Click *More* to display a list of all available destinations. Check the checkbox for each destination you want to include in the destination menu list.




Filter Select *Filter* from the Gear menu to display a check list of encoder presets. Check the presets you want to display in the Encoder presets menu. Click *Save* when finished.




New Preset Select *New Preset* from the Gear menu to create a new encoder preset. Enter a name for your new preset and click OK. (See [Creating New Presets](#)).



View Details Select *View Details* from the Gear menu to modify an encoder preset. (See *Creating New Presets*). One important option is Strict Constant Bitrate. When checked, the bitrate is strictly held at the bitrate entered in *Average bit rate*.




More Click the *More* button to display a check list of destinations. Check the destinations you want to display in the Destination menu. Click *Save* when finished.



Multicast and Unicast

You can select Multicast or unicast from the Destination menu. Multicast lets you broadcast to multiple computers simultaneously. Unicast lets you broadcast to a specific computer.



You need to create an SDP File, and you must do so every time you change any option on this page (including the encoder preset). To create an SDP file click the gear icon and select *Save SDP File*, navigate to the desired location, and click *Save* in the Save File dialog window. The SDP file must be given to the user to place on the computer that receives your broadcast.

During multicast, your broadcasting computer sends data across your local network, identifying it as a broadcast that it has no specific destination. Since many applications could be doing the same thing, the broadcasting computer must have a unique way of defining the data that is being multicast. This enables clients to choose between the available multicast streams.

The multicast protocol uses unique addresses, one for video and one for audio. Although these unique addresses look like TCP/IP addresses, they are not. Instead, they provide a way to define uniqueness among all multicast data flowing over the network. Once the broadcasting computer is streaming this data through the local network, any computer on the network can receive it.

The SDP file becomes the glue between your broadcast computer and the viewer computers. The SDP file contains multicast addresses, encoding format, and other important information.

Flash RTMP Server


Wirecast can stream to an RTMP/ H.264-compatible streaming server (Flash Media Server, Wowza Media Server, etc.). Flash Players earlier than Flash 9, Update 3 (Dec 2007), may not be able to view the H.264 based streams.

To configure Flash Media Streaming, follow these steps:

1. Select Destination > RTMP Server.
2. Select an encoder.
3. Enter the Address to the RTMP server. (This is the same as the FMS URL in Flash Media Server.) The default RTMP port is 1935, but you may need to configure your firewall to allow connections on this port.
4. Wirecast can import a Flash Media Encoder configuration file (XML file). Click Open FMLE XML File, and navigate to the configuration file and select either version 2.5 or version 3.0. Wirecast reads the Address and Stream information from that file. Many online streaming services offer FMLE configuration files which Wirecast can use.

Note: Only the Address and Stream information from the XML configuration file is used. No Encoding information is imported.

5. Click OK to save your settings:



CDN Partners

Listed below are the Content Distribution Network (CDN) partner destinations available in Wirecast. Most destinations share a common user interface and only require a user name and password. Destinations that do not conform to this paradigm, or require additional parameters, are presented separately.

Note: The list of CDN partners in Wirecast is subject to change at any time.

Flash To Bambuser, Churchstreaming.tv, DaCast Streaming Services, High School Cube, iNK Barrel Video, Livebeats, make.tv, Meridix Sports Network, Netbriefings, ShowCaster, Streaming Media Hosting, StreamVu, Stretch Internet, Sunday Streams, Tulix, Ustream

To stream to one of these CDN partners, follow these steps:

1. Select a CDN partner from the Destination menu.
2. Select an encoder.
3. Enter your username.
4. Click *Authenticate* to enter your password and generate the RTMP URL. You only need to do this one time because Wirecast stores the channel information for future streams. The default RTMP port is 1935. You may need to configure your firewall to enable connections on this port.

Note: If you do not have a username and password, you can sign up with a CDN partner by clicking *Sign Up*.

5. Select your channel.
6. Optionally, enter a Stream Delay value. This provides a time buffer between your live stream from Wirecast and the actual broadcast itself. You can set the delay from 0 to 999 seconds. However, greater delays require greater memory use. The amount of memory used is displayed when you enter the amount of delay.

7. Click OK when finished.

The screenshot shows the 'Broadcasting' settings window in Wirecast. The window is divided into several sections. At the top, there are three dropdown menus: 'Name' (set to 'Not Configured'), 'Destination' (set to 'Bambuser'), and 'Encoding' (set to 'Limelight H.264 1080p 16:9 (1920x1080)'). To the right of the 'Destination' dropdown is a 'More...' button. Below these is a horizontal line. The middle section contains a 'Username' text field, a 'Channel' dropdown menu, and an 'Authenticate' button. To the right of these fields is a green square logo with a white 'b' and the text 'Sign Up' below it. Below this section is another horizontal line. The bottom section contains 'Bitrate: 4242 k', 'Location:', and 'Stream Delay: 0 seconds'. At the very bottom are 'OK' and 'Cancel' buttons. Annotations with lines pointing to specific elements are as follows:

- Line from 'More...' button to 'Select a CDN partner'
- Line from 'More...' button to 'Select an encoder'
- Line from 'Authenticate' button to 'Enter user name'
- Line from 'Authenticate' button to 'Click Authenticate and enter password'
- Line from 'Channel' dropdown to 'Select Channel'
- Line from 'Stream Delay' field to 'Enter delay (optionally)'
- Line from 'OK' button to 'Click OK'

Flash To Microsoft Azure, Brightcove, Limelight, Sermon.net

To stream to one of these CDN partners, follow these steps:

1. Select a CDN partner from the Destination menu.
2. Select an encoder.
3. Enter the domain name or IP address (this is provided by the CDN partner).
4. Enter the stream name of your broadcast (this is provided by the CDN partner).
5. Click *Set Credentials* to enter your password and generate the RTMP URL. You only need to do this one time because Wirecast stores the channel information for future streams. The default RTMP port is 1935. You may need to configure your firewall to enable connections on this port.

Note: If you do not have a stream name and password, you can sign up with the CDN partner by clicking *Learn More*.

6. Optionally, enter a Stream Delay value. This provides a time buffer between your live stream from Wirecast and the actual broadcast itself. You can set the delay from 0 to 999 seconds. However, greater delays require greater memory use. The amount of memory used is displayed when you enter the amount of delay.
7. Click OK when finished.

The screenshot shows the Wirecast configuration dialog for streaming to a CDN partner. The dialog is titled "Name: Not Configured". It has several sections:

- Destination:** A dropdown menu showing "Brightcove". A "More..." button is next to it.
- Encoding:** A dropdown menu showing "H.264 720p 16:9 (1280x720)". A gear icon is next to it.
- Address:** A text box for entering the domain name or IP address.
- Stream:** A text box for entering the stream name.
- Set Credentials...** A button to enter credentials and generate the RTMP URL.
- Bitrate:** A label showing "2217 k".
- Location:** A label.
- Stream Delay:** A text box with "0" and a label "seconds".
- OK** and **Cancel** buttons at the bottom.

Annotations with arrows point to the following elements:

- Select host server (points to the Destination dropdown)
- Select an encoder (points to the Encoding dropdown)
- Enter Address (points to the Address text box)
- Enter Stream name (points to the Stream text box)
- Click Set Credentials (points to the Set Credentials button)
- Enter delay (optionally) (points to the Stream Delay input field)
- Click OK (points to the OK button)

Flash To Akamai

To stream to Akamai, follow these steps:

1. Select *Akamai* from the Destination menu.
2. Select an encoder.
3. Enter your Akamai Stream ID and Event Name.
4. Enter your Akamai Angle and Video Rate.
5. Enter your user name.
6. Click *Authenticate* to enter your password and generate the RTMP URL. You only need to do this one time because Wirecast stores the channel information for future streams. The default RTMP port is 1935. You may need to configure your firewall to enable connections on this port.

Note: If you do not have a username and password, you can sign up with Akamai by clicking the Akamai icon, or by clicking *Sign Up*.

7. Optionally, enter a Stream Delay value. This provides a time buffer between your live stream from Wirecast and the actual broadcast itself. You can set the delay from 0 to 999 seconds. However, greater delays require greater memory use. The amount of memory used is displayed when you enter the amount of delay.
8. Click OK.

The screenshot shows the 'Flash To Akamai' configuration window. The 'Name' field is 'Not Configured'. The 'Destination' dropdown is set to 'Akamai'. The 'Encoding' dropdown is set to 'Akamai: 1080p 16:9'. Below these are input fields for 'Stream ID', 'Event Name', 'Angle', and 'Video Bit Rate'. A 'Username' field is followed by an 'Authenticate' button and a 'Sign Up' link. At the bottom, there are fields for 'Bitrate' (4242 k), 'Location', and 'Stream Delay' (set to 0 seconds). The Akamai logo is centered in the background. Annotations on the right side of the image provide instructions for each field and button.

Field/Control	Instruction
Destination: Akamai	Select Akamai
Encoding: Akamai: 1080p 16:9	Select an encoder
Stream ID: []	Enter Stream ID and Event Name
Event Name: []	
Angle: []	Enter angle and video rate
Video Bit Rate: []	
Username: []	Enter a user name
Authenticate button	Click Authenticate and enter password
Stream Delay: 0 seconds	Enter delay (optionally)

Flash To TwitchTV

To stream to TwitchTV, follow these steps:

1. Select *TwitchTV* from the Destination menu.
2. Select an encoder.
3. Enter your TwitchTV username.
4. Click *Authenticate* to enter your password and generate the RTMP URL. You only need to do this one time because Wirecast stores the channel information for future streams. The default RTMP port is 1935. You may need to configure your firewall to enable connections on this port.

Note: If you do not have a username and password, you can sign up with TwitchTV by clicking the TwitchTV icon or by clicking *Sign Up*.

5. A default path is automatically provided for the RTMP Ingest URL. Use this URL unless you have received a different one from TwitchTV.
6. Optionally, enter a Stream Delay value. This provides a time buffer between your live stream from Wirecast and the actual broadcast itself. You can set the delay from 0 to 999 seconds. However, greater delays require greater memory use. The amount of memory used is displayed when you enter the amount of delay.
7. Click *OK* when finished

The screenshot shows the Wirecast configuration window for TwitchTV. The window has a light gray background and a white border. It contains several sections with labels and input fields. On the right side, there are five lines of text with arrows pointing to specific elements in the window: 'Select TwitchTV' points to the 'Destination' dropdown menu; 'Select Encoder' points to the 'Encoding' dropdown menu; 'Enter Username' points to the 'Username' input field; 'Click Authenticate and enter password' points to the 'Authenticate' button; and 'Enter delay (optionally)' points to the 'Stream Delay' input field. The 'Name' field is set to 'Not Configured'. The 'Destination' dropdown is set to 'TwitchTV'. The 'Encoding' dropdown is set to 'Twitch 540p30'. The 'Username' field is empty. The 'RTMP Ingest Url' field is set to 'rtmp://live.twitch.tv/app'. Below the 'RTMP Ingest Url' field, there is a link that says 'Find the closest ingest server'. The 'Bitrate' is set to '1596 k'. The 'Location' is set to 'rtmp://live.twitch.tv/app :'. The 'Stream Delay' is set to '0 seconds'. There is a 'Sign Up' link next to the Twitch logo.

Name: Not Configured

Destination: TwitchTV

Encoding: Twitch 540p30

Username:

RTMP Ingest Url: rtmp://live.twitch.tv/app

Bitrate: 1596 k

Location: rtmp://live.twitch.tv/app :

Stream Delay: 0 seconds

Authenticate

Find the closest ingest server

Sign Up

Select TwitchTV

Select Encoder

Enter Username

Click Authenticate and enter password

Enter delay (optionally)

Flash To YouTube

To stream to YouTube, follow these steps:

1. Select *YouTube* from the Destination menu.
2. Select an encoder.

Note: YouTube may not yet support OpenIDs via this API. The solution is to download the FMLE configuration file from YouTube and use the Flash Media Server interface.

3. Click *Authenticate* to enter your username and password and generate the RTMP URL. You only need to do this one time because Wirecast stores the channel information for future streams. The default RTMP port is 1935. You may need to configure your firewall to enable connections on this port.

Note: If you do not have a username and password, you can sign up with YouTube by clicking the YouTube icon or by clicking *Sign Up*.

4. Select your YouTube event.
5. Optionally, enter a Stream Delay value. This provides a time buffer between your live stream from Wirecast and the actual broadcast itself. You can set the delay from 0 to 999 seconds. However, greater delays require greater memory use. The amount of memory used is displayed when you enter the amount of delay.
6. Click *OK*.

The screenshot shows the Wirecast configuration window for streaming to YouTube. The interface includes the following elements:

- Name:** Not Configured
- Destination:** YouTube (with a "More..." button)
- Encoding:** Authenticate for Encoding Presets (with a settings icon)
- Username:** (with an "Authenticate" button)
- Event:** Authenticate for Event List (with a "Use backup server" checkbox)
- YouTube Logo:** Broadcast Yourself™ (with a "Sign Up" link)
- Bitrate:** 1596 k
- Location:** (empty field)
- Stream Delay:** 0 seconds

Annotations on the right side of the image point to the following elements:

- Select YouTube (points to the Destination dropdown)
- Select an encoder (points to the Encoding dropdown)
- Click Authenticate then enter username and password (points to the Authenticate button)
- Select Event (points to the Event dropdown)
- Enter delay (optionally) (points to the Stream Delay input field)

Flash To Zixi

To stream to Zixi, follow these steps:

1. Select *Zixi* from the Destination menu.
2. Select an encoder.
3. Enter Zixi connection information.
4. Enter your Zixi channel name and password.
5. Click *apply* to generate the RTMP URL. You only need to do this one time because Wirecast stores the channel information for future streams. The default RTMP port is 1935. You may need to configure your firewall to enable connections on this port.

Note: If you do not have a username and password, you can sign up with Zixi by clicking the Zixi icon, or by clicking *Sign Up*.

6. Optionally, enter a Stream Delay value. This provides a time buffer between your live stream from Wirecast and the actual broadcast itself. You can set the delay from 0 to 999 seconds. However, greater delays require greater memory use. The amount of memory used is displayed when you enter the amount of delay.
7. Click *OK*.

The screenshot shows the 'Flash To Zixi' configuration window in Wirecast. The window is divided into several sections. At the top, there are three dropdown menus: 'Name' (set to 'Not Configured'), 'Destination' (set to 'Zixi'), and 'Encoding' (set to 'H.264 720p 16:9 (1280x720)'). To the right of these dropdowns are 'More...' and 'Settings' icons. Below these are input fields for 'Broadcaster Address', 'Broadcaster Port' (set to 2088), 'Latency [milliseconds]' (set to 4000), 'Channel Name', and 'Password'. An 'Apply' button is located below these fields. To the right of the input fields is the Zixi logo and a 'Sign Up' link. At the bottom, there are fields for 'Bitrate' (set to 2217 k), 'Location', and 'Stream Delay' (set to 0 seconds). Annotations with lines pointing to specific elements are as follows: 'Select YZixi' points to the 'Destination' dropdown; 'Select an encoder' points to the 'Encoding' dropdown; 'Enter Zixi connection info' points to the 'Broadcaster Address' and 'Broadcaster Port' fields; 'Enter Channel Name and Password' points to the 'Channel Name' and 'Password' fields; 'Click Apply' points to the 'Apply' button; and 'Enter delay (optionally)' points to the 'Stream Delay' field.

Name: Not Configured

Destination: Zixi

Encoding: H.264 720p 16:9 (1280x720)

Broadcaster Address:

Broadcaster Port: 2088

Latency [milliseconds]: 4000

Channel Name:

Password:

Apply

Bitrate: 2217 k

Location:

Stream Delay: 0 seconds

Select YZixi

Select an encoder

Enter Zixi connection info


Enter Channel Name and Password

Click Apply


Enter delay (optionally)

Streaming


To stream your presentation, click the *Stream* button at the top of the Main window.



If you have not already selected a destination and logged into it, a dialog box displays. Select a destination, log in when asked to do so, then click OK.



The Stream LED will blink until a connection is made. Once you are connected the LED turns full on and a red box is placed around the Stream button. If you cannot connect an error message will display.



Connection strength bars are displayed on the right. Fewer bars indicates a weaker (slower) connection.



If the connection is ever broken, the green bars are reduced to a single red bar, then immediately a *no connection* icon is displayed in place of the bars.



When the connection recovered, the *no connection* icon is replaced with the green bars.

Click *Stream* again to stop streaming. You can also record your broadcast by clicking *Record*.

Record To Disk

If you want to archive your stream, you can use the Record To Disk destination.


Note: Wirecast auto-saves your Stream/recording every 20 seconds.

To record to disk, follow these steps:


1. Click the Record button at the top of the Wirecast Main window.



2. When the dialog box displays, select *Record to Disk* and click *OK*.



3. When the Output Settings window displays, Select *Record To Disk* (for MP4 or Windows Media, MOV)
4. Select an encoder.
5. Click Browse or enter the path to where you want your recording located.
6. Check the Auto Increment Filenames checkbox (optionally), if you want your filename to have an incremental number appended to the end of it. This causes a new file to be created every time you start recording to disk. If you do not check this checkbox, then your previous file is overwritten.
7. Click OK.



Encoder Presets

Introduction

STUDIO

Wirecast supports a wide variety of encoders (also known as codecs).

An encoder is a program that compresses the audio and/or video output of Wirecast for broadcast. Without an encoder, the uncompressed data is too large to successfully broadcast across a network. This is why encoders are so important.

The settings for encoders range from simple to very complex. Because of this, Wirecast offers presets of the most common settings for encoders. This provides a starting point, reduces complexity, and enables you to experiment and adjust settings as you test your broadcast.

Note: Encoder Presets can also be edited from the Output Settings window. To do this select *Output > Output Settings*, click the gear icon, then choose *View Details* from the drop-down menu.

Topics

- [The Encoder Presets Window](#)
-
- [MainConcept H.264](#)
- [x264](#)

The Encoder Presets Window

To open the Encoder Presets window, select *Window > Encoder Presets*. The Encoder Preset menu at the top of the window provides a list of encoder presets. Select a preset to edit from this list.

Creating New Presets

The default encoder presets cannot be changed. However, you can make a copy of any preset, modify it as needed, and save it under a new name. You can refer back to the default presets at any time since they are never modified.

To create a new preset, you must make a copy of an existing preset. To do this, select an existing preset from the Encoder Presets menu that is close to what you what you need, change settings as needed, then click *Save As* to save the preset with a new name.

Profile Options

Many encoder presets enable you to select one of three profiles: Baseline, Main, or High.

Baseline Profile (BP) Baseline profile is primarily for low-cost applications that require additional data loss robustness. This profile is used in some video conferencing and mobile applications. It includes all features supported in the Constrained Baseline Profile, plus three additional features used for loss robustness (or for other purposes such as low-delay multi-point video stream compositing). The importance of this profile has faded somewhat since the definition of the Constrained Baseline Profile in 2009. All Constrained Baseline Profile bitstreams are also considered to be Baseline Profile bitstreams, since these two profiles share the same profile identifier code value.

Main Profile (MP) The Main profile is used for standard-definition digital TV broadcasts that use the MPEG-4 format as defined in the DVB standard. It is not, however, used for high-definition television broadcasts, since the importance of this profile faded when the High Profile was developed in 2004 for that application.


High Profile (HiP) The High profile is the primary profile used for broadcast and disc storage applications, particularly for high-definition television applications. For example, this profile is used by the Blu-ray Disc storage format and the DVB HDTV broadcast service.

MainConcept H.264

STUDIO

To modify a MainConcept H.264 preset, follow these steps:

1. Open the Encoder Presets window.
2. Select an encoder preset from the Encoder Presets menu.



Note: To use a newly created preset (See [Creating New Presets](#)).

3. Check the Video Encoding checkbox. When checked, the video for your broadcast is encoded. When unchecked, a blank video screen is provided. This is the preferred method of producing audio-only broadcasts.
4. Select the Main Concept H.264 encoder from the Encoder menu.
5. Enter the width of your broadcast video.
6. Enter the height of your broadcast video.
7. Select the desired frames per second (FPS) of your broadcast. This value is a target value for the encoder and the exact value is not guaranteed.
8. Enter the average bit rate in Kbits (1000 bits) per second. This is the target bit rate of your video. Higher numbers provide better quality. The connection speed of your audience is a significant factor in determining your target bit rate. The encoder

compresses the video to approximate this target. However, at different times during your broadcast the bit rate may be higher or lower than the target rate.

9. Select an encoder profile from the Profile menu. Three profiles are provided: Baseline, Main, and High. The Baseline profile is commonly used in mobile applications. It is also used in other applications which operate with limited processing power, storage capacity, and/or bandwidth. The Main profile is appropriate for general-purpose applications of broadcast media, such as high-bandwidth Internet broadcasting. The High profile provides the highest broadcast quality encoding.
10. Key Frame (optionally) allows you to enter the number of frames. A movie is a sequence of images and each image is called a frame. To compress video data, most encoders take a frame and make it a reference (also known as a key). This keyframe is sent as part of the broadcast, and all of the data after that keyframe is relative to it. The benefit of this is that the compressor only needs to send what has changed since the last keyframe. The main drawback of this is that over time it becomes harder for the encoder to distinguish the frame-difference information, especially if there is a lot of motion in the video. Another drawback is if your viewer's computer misses a keyframe, the video is distorted until the next keyframe is sent. However, you can control how often the encoder makes a new keyframe by setting the number of frames. The more keyframes you broadcast, the more bandwidth required and less compression, but results in better quality video.
11. Check (optionally) the Timecode Every checkbox and enter the number of frames between timecodes. Wirecast can generate timecodes embedded in the flash stream. If a frames value of zero is entered, the timecode is never sent. Wirecast sends metadata along with the frames. This data looks like an ONFI call. Various timecodes and timestamps are also sent with the stream.
12. Check (optionally) Strict Constant Bitrate. When checked, it forces the Average bit rate (see item 8 above) to maintain the exact bit rate entered. CBR pads the data (when necessary) to meet exact bitrate specified. Disabling CBR can result in slightly improved quality and decrease file size, but at the cost of greater bitrate fluctuations which could prove troublesome for certain streaming destinations. Selecting this option for recording is not recommended because it can result in decreased quality and larger files, with no real benefit.
13. Check (optionally) Keyframe aligned. When checked, it facilitates adaptive bitrate streaming by ensuring that keyframes from multiple streams are in sync, along with the keyframes timestamp, DTS and PTS values. But this is true only if those other streams also have the option turned on and have the same keyframe interval. To accomplish this, Wirecast disables scene detection and manually inserts the keyframe at the exact keyframe interval specified. Therefore, to ensure quality and smooth switching in the player, the keyframe interval should be in the 1 to 4 second range. When Keyframe Aligned is enabled, absolute timestamp is also enabled.
14. Check (optionally) the Audio Encoding (AAC) checkbox. When checked, the audio for your broadcast is included. When unchecked, audio is absent. This is the preferred method of producing video-only broadcasts because the presence of silent audio uses bandwidth.

15. Select the number of channels: Mono or Stereo. Mono uses less bandwidth than stereo, but stereo is more pleasing to the listener.
16. Select the audio bit rate, in Kbits (1000 bits) per second, from the Target Bit Rate menu. This is the target bit rate of your audio. Higher numbers provide better quality. The connection speed of your audience is a significant factor in determining your target bit rate. The encoder compresses the audio to approximate this target. However, at different times during your broadcast the bit rate may be higher lower than the target rate. The total broadcast bit rate is a function of video bit rate plus audio bit rate.
17. Select the audio sample rate, in kHz (1000 Hz) per second, from the Sample Rate menu. This value specifies how many thousands of times per second to sample the audio in the broadcast. Higher values provide better quality sound, but at greater bandwidth.
18. Click Save to save your settings.


x264

STUDIO

Note: The x264 implementation of the H.264 standard results in better quality and lower CPU usage for any given bitrate, but at the cost of higher memory usage. The default implementation is based on the Mainconcept codec and uses less memory.

To modify a Flash x264 preset, follow these steps:

1. Open the Encoder Presets window.
2. Select an encoder preset from the Encoder Presets menu.



Note: To use a newly created preset (See [Creating New Presets](#)).

3. Check the Video Encoding checkbox. When checked, the video for your broadcast is encoded. When unchecked, a blank video screen is provided. This is the preferred method of producing audio-only broadcasts.
4. Select x264 for Encoder.
5. Enter the width of your broadcast video.
6. Enter the height of your broadcast video.

7. Select the desired frames per second (FPS) of your broadcast. This value is a target value for the encoder and the exact value is not guaranteed.
8. Enter the average bit rate in Kbits (1000 bits) per second. This is the target bit rate of your video. Higher numbers provide better quality. The connection speed of your audience is a significant factor in determining your target bit rate. The encoder compresses the video to approximate this target. However, at different times during your broadcast the bit rate may be higher lower than the target rate.
9. Select encoding quality (*Ultra fast* to *Very slow* encoding). Slower encoding results in better quality.
10. In the *x264 command line options* edit box, enter any command line options you want included. A list of the command line options can be found at: http://mewiki.project357.com/wiki/X264_Settings.
11. Select an encoder profile from the Profile menu. Three profiles are provided: Baseline, Main, and High. The Baseline profile is commonly used in mobile applications. It is also used in other applications which operate with limited processing power, storage capacity, and/or bandwidth. The Main profile is appropriate for general-purpose applications of broadcast media, such as high-bandwidth Internet broadcasting. The High profile provides the highest broadcast quality encoding.
12. Key Frame (optionally) allows you to enter the number of frames. A movie is a sequence of images and each image is called a frame. To compress video data, most encoders take a frame and make it a reference (also known as a key). This keyframe is sent as part of the broadcast, and all of the data after that keyframe is relative to it. The benefit of this is that the compressor only needs to send what has changed since the last keyframe. The main drawback of this is that over time it becomes harder for the encoder to distinguish the frame-difference information, especially if there is a lot of motion in the video. Another drawback is if your viewer's computer misses a keyframe, the video is distorted until the next keyframe is sent. However, you can control how often the encoder makes a new keyframe by setting the number of frames. The more keyframes you broadcast, the more bandwidth required and less compression, but results in better quality video.
13. Check (optionally) Strict Constant Bitrate. When checked, it forces the Average bit rate (see item 8 above) to maintain the exact bit rate entered. CBR pads the data (when necessary) to meet exact bitrate specified. Disabling CBR can result in slightly improved quality and decrease file size, but at the cost of greater bitrate fluctuations which could prove troublesome for certain streaming destinations. Selecting this option for recording is not recommended because it can result in decreased quality and larger files, with no real benefit.
14. Check (optionally) Keyframe aligned. When checked, it facilitates adaptive bitrate streaming by ensuring that keyframes from multiple streams are in sync, along with the keyframes timestamp, DTS and PTS values. But this is true only if those other streams also have the option turned on and have the same keyframe interval. To accomplish this, Wirecast disables scene detection and manually inserts the keyframe at the exact keyframe interval specified. Therefore, to ensure quality and smooth switching in the player, the keyframe interval should be in the 1 to 4

second range. When Keyframe Aligned is enabled, absolute timestamp is also enabled.

15. Check (optionally) the Timecode Every checkbox and enter the number of frames between timecodes. Wirecast can generate timecodes embedded in the flash stream. If a frames value of zero is entered, the timecode is never sent. Wirecast sends metadata along with the frames. This data looks like an ONFI call. Various timecodes and timestamps are also sent with the stream.
16. Check (optionally) the Audio Encoding (AAC) checkbox. When checked, the audio for your broadcast is included. When unchecked, audio is absent. This is the preferred method of producing video-only broadcasts because the presence of silent audio uses bandwidth.
17. Select the number of channels: Mono or Stereo. Mono uses less bandwidth than stereo, but stereo is more pleasing to the listener.
18. Select the audio bit rate, in Kbits (1000 bits) per second, from the Target Bit Rate menu. This is the target bit rate of your audio. Higher numbers provide better quality. The connection speed of your audience is a significant factor in determining your target bit rate. The encoder compresses the audio to approximate this target. However, at different times during your broadcast the bit rate may be higher lower than the target rate. The total broadcast bit rate is a function of video bit rate plus audio bit rate.
19. Select the audio sample rate, in kHz (1000 Hz) per second, from the Sample Rate menu. This value specifies how many thousands of times per second to sample the audio in the broadcast. Higher values provide better quality sound, but at greater bandwidth.
20. Click Save to save your settings.

Making Great Presentations

Introduction

These topics provide helpful information about how to prepare for creating great presentations.

Topics

- *Overview*
- *High Quality Audio*
- *Good Lighting*
- *Broadcast Settings*

Overview

There are many ways to make a good live event even better. But this appendix focuses on two main things to remember about video streaming:

- **High Quality Audio Input** Great looking video with poor audio input appears unprofessional.
- **Good Lighting** Poor lighting can ruin an otherwise excellent live event. If you are doing chroma keying, this may become the most important part of your setup.

When video is saved to disk or sent over the network, it needs to be compressed. The compression process is done by encoders (codecs) which are optimized to work with clean input data. This means that if the audio or video is muddy to start with, it remains muddy after compression. Some codecs may even highlight poor input because the algorithm is built to look for differences.

Your goal should be to give the best possible quality audio and video to the compression process as possible. This means making sure what you see in the Live area is the best possible quality because Wirecast takes exactly what you see and sends it to the codecs.

High Quality Audio

Audio has an artistic aspect to it. You can make a great live event even better by remembering to focus on a few details. Here are some suggestions on producing clean audio.

- **Use a Good Microphone** Though this may sound obvious, a good microphone can make a huge difference. Most DV cameras have an audio input for an external microphone. Use this, whenever possible, instead of the built-in microphone that comes with the camera. Built-in microphones are usually not good quality and tend to pick up hum from the electronics inside the camera. Even when it is not a great microphone, an external microphone almost always sound better.
- **Use a Microphone Splitter** If you are doing an interview with one camera, you can use two microphones with a splitter (less than \$5). This often gives better results than one omni-directional microphone at a distance. You can also use a dual lapel microphone with a splitter.
- **Position the Microphone Properly** Place any microphone as close to the sound source as possible, even when using omni-directional microphones, because sound volume decreases greatly the farther away the microphone is placed. Stronger signals coming into the microphone results in better quality.
- **Use Lapel Microphones** Even inexpensive (less than \$20) lapel microphones can make a huge difference because it places the microphone much closer to the person speaking.
- **Control Environmental Noise** If a chair squeaks, use a different one. If you have a wood floor and you can hear people shuffling their feet as they talk, put down a rug. Do whatever it takes to keep noise at a minimum. Microphones pick up everything.

Good Lighting

Do not underestimate the power of lighting. When an event is shot outdoors, a great deal of attention goes into lighting. For professionals, lighting is viewed as an artistic task. Many people make their living controlling lighting, so there is a lot to it. Here are a few suggestions to help you obtain reasonably good lighting:

- If you are using only one lighting source, do not shine it directly on your subject. You should diffuse the light by bouncing it off of a wall or by shining it through opaque material.
- Avoid deep shadows. Make sure you fill all areas of your subject with light. Sometimes this requires adjusting the light to bounce off a different wall or use two lights. Placing a light low and another one high is often a good way to light evenly.
- Do not light too evenly. If you evenly light a set, you may actually be worse off than not lighting the set at all. Take a sample shot and see if it looks natural. Good lighting usually has a little more light coming from above than any other direction. You should very rarely light just from below a subject.

- Beware of having too much light on your subject. If your subjects are people and you must use a lot of light, use make-up to compensate for the overly bright lighting. This is not necessarily a bad thing, but you must choose how much effort you want to go through to make a good live event. If your lighting balance is excellent, you will can avoid make-up on your subjects. The key in adjusting the lighting is to look at your subject and make sure they do not look washed out.
- Watch professional events and learn from them. As you watch, notice the lighting instead of watching the program. Notice how they employ the suggestions listed above.

These guidelines might seem to suggest subtle improvements, but good lighting can make an amateur video look professional and a professional video look fabulous. The important thing to remember is that one or two properly placed lights makes a huge difference in the quality of your live event.

Triangular Lighting

One advanced and very effective approach to good lighting is known as *triangular lighting* (or *three light setup*). Although this may sound complicated, it is actually quite simple. It involves setting up three lights (sometimes using natural light as one of the light sources), in a configuration that achieves a good balance. Here are the main elements of Triangular Lighting:

- **Main Light (Key Light)** This is the strongest of your lights and does most of the work. This light normally comes from one side of the camera (the left, for example) and is slightly raised. However, using just the main light results in shadowing.
- **Fill Light** This is a soft light placed directly in front of the subject. It removes shadows and fills in the image. It is usually direct and usually comes from the same direction as the camera (or just to the side and behind it). It could be, for example, placed on the same level as the head of a person you are lighting. If you use only a fill light, your subject might appear too dark. The only purpose of a fill light is to add to the main light by filling in shadows. If your key light comes from the left of your camera, your fill light should come from the right, and vice versa.
- **Back Light (Rim Light)** This light is directed from behind the subject and above it. This is the hardest light to explain, but the best way is to describe it as an accent of your subject. If you look at a typical high school yearbook picture, you will notice that the top-left (or top-right) part of each head shot has a highlight of light in it. This light is the *back light*. It is also called a *rim light* because it makes a slight rim around the edge of the head of your subject. This light normally comes from behind and above the subject, and it is focused. Make sure it is not directed at the camera.

Most serious lighting starts with these three basic lights. There are also some great Websites that describe these techniques in great detail.

Broadcast Settings

Once you have good video and audio coming into Wirecast, the final item of importance is make sure the Broadcast Settings are configured correctly for your presentation. Though there are many broadcast parameters to modify, there are three that are the most important: bandwidth, motion, and encoder settings.

Bandwidth

The first item of importance is knowing how much bandwidth is available. Bandwidth is how much data you can broadcast from your computer. This depends on the speed of your network connection and the type of connection your viewers are using. More specifically, it is the minimum speed between you and all of your viewers. For example, if you have one viewer who is using a dial-up modem, for that viewer to see good quality you must broadcast at Modem speed.

Thus, you must know who your viewers are and what kind of connection they have. This may be difficult to know because you must determine if their connection is cable modem or DSL and whether or not they reside on your local network.

In some situations, you are broadcasting for just your local network (in an office building, for example). In this case you should discuss your plans with your network administrator and verify that you will not disrupt the network with your broadcasts. Ask them what your upper limit bandwidth should be. Your available bandwidth is the minimum of what you can upload, combined with what your viewers can download.

Motion

Once you know your bandwidth, you need to decide whether or not your video contains a lot of motion. Motion is how much things move around in your video presentations. An interview is considered low motion. A sports event, however, would probably be high motion. Wirecast comes configured with defaults to help ease your configuration task. Choose a default configuration that meets your motion (and bandwidth) constraints.

Encoder Settings

The parameters of the encoders are quite technical and can be overwhelming. It is beyond the scope of this document to describe the delicate balance required in setting them. There are professionals who fine-tune encoders to do exactly what is required. The Wirecast default settings are generally optimal for the various network environments. (See [Encoder Presets](#) for information on changing the encoder settings.)

Acknowledgments

Acknowledgments

Overview

Portions of this software may utilize the following copyrighted material, the use of which is hereby acknowledged:

- *Darwin streaming server*
- *FFmpeg Project*

Darwin streaming server

APPLE PUBLIC SOURCE LICENSE Version 2.0 - August 6, 2003 Please read this License carefully before downloading this software.

By downloading or using this software, you are agreeing to be bound by the terms of this License. If you do not or cannot agree to the terms of this License, please do not download or use the software.

1. General; Definitions. This License applies to any program or other work which Apple Computer, Inc. ("Apple") makes publicly available and which contains a notice placed by Apple identifying such program or work as "Original Code" and stating that it is subject to the terms of this Apple Public Source License version 2.0 ("License"). As used in this License: 1.1 "Applicable Patent Rights" mean: (a) in the case where Apple is the grantor of rights, (i) claims of patents that are now or hereafter acquired, owned by or assigned to Apple and (ii) that cover subject matter contained in the Original Code, but only to the extent necessary to use, reproduce and/or distribute the Original Code without infringement; and (b) in the case where You are the grantor of rights, (i) claims of patents that are now or hereafter acquired, owned by or assigned to You and (ii) that cover subject matter in Your Modifications, taken alone or in combination with Original Code.

1.2 "Contributor" means any person or entity that creates or contributes to the creation of Modifications.

1.3 "Covered Code" means the Original Code, Modifications, the combination of Original Code and any Modifications, and/or any respective portions thereof.

1.4 "Externally Deploy" means: (a) to sublicense, distribute or otherwise make Covered Code available, directly or indirectly, to anyone other than You; and/or (b) to use Covered Code, alone or as part of a Larger Work, in any way to provide a service,

including but not limited to delivery of content, through electronic communication with a client other than You.

1.5 "Larger Work" means a work which combines Covered Code or portions thereof with code not governed by the terms of this License.

1.6 "Modifications" mean any addition to, deletion from, and/or change to, the substance and/or structure of the Original Code, any previous Modifications, the combination of Original Code and any previous Modifications, and/or any respective portions thereof. When code is released as a series of files, a Modification is: (a) any addition to or deletion from the contents of a file containing Covered Code; and/or (b) any new file or other representation of computer program statements that contains any part of Covered Code.

1.7 "Original Code" means (a) the Source Code of a program or other work as originally made available by Apple under this License, including the Source Code of any updates or upgrades to such programs or works made available by Apple under this License, and that has been expressly identified by Apple as such in the header file(s) of such work; and (b) the object code compiled from such Source Code and originally made available by Apple under this License.

1.8 "Source Code" means the human readable form of a program or other work that is suitable for making modifications to it, including all modules it contains, plus any associated interface definition files, scripts used to control compilation and installation of an executable (object code).

1.9 "You" or "Your" means an individual or a legal entity exercising rights under this License. For legal entities, "You" or "Your" includes any entity which controls, is controlled by, or is under common control with, You, where "control" means (a) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (b) ownership of fifty percent (50%) or more of the outstanding shares or beneficial ownership of such entity.

2. Permitted Uses; Conditions & Restrictions. Subject to the terms and conditions of this License, Apple hereby grants You, effective on the date You accept this License and download the Original Code, a world-wide, royalty-free, non-exclusive license, to the extent of Apple's Applicable Patent Rights and copyrights covering the Original Code, to do the following: 2.1 Unmodified Code. You may use, reproduce, display, perform, internally distribute within Your organization, and Externally Deploy verbatim, unmodified copies of the Original Code, for commercial or non-commercial purposes, provided that in each instance: (a) You must retain and reproduce in all copies of Original Code the copyright and other proprietary notices and disclaimers of Apple as they appear in the Original Code, and keep intact all notices in the Original Code that refer to this License; and (b) You must include a copy of this License with every copy of Source Code of Covered Code and documentation You distribute or Externally Deploy, and You may not offer or impose any terms on such Source Code that alter or restrict this License or the recipients' rights hereunder, except as permitted under Section 6.

2.2 Modified Code. You may modify Covered Code and use, reproduce, display, perform, internally distribute within Your organization, and Externally Deploy Your Modifications and Covered Code, for commercial or non-commercial purposes,

provided that in each instance You also meet all of these conditions: (a) You must satisfy all the conditions of Section 2.1 with respect to the Source Code of the Covered Code; (b) You must duplicate, to the extent it does not already exist, the notice in Exhibit A in each file of the Source Code of all Your Modifications, and cause the modified files to carry prominent notices stating that You changed the files and the date of any change; and (c) If You Externally Deploy Your Modifications, You must make Source Code of all Your Externally Deployed Modifications either available to those to whom You have Externally Deployed Your Modifications, or publicly available. Source Code of Your Externally Deployed Modifications must be released under the terms set forth in this License, including the license grants set forth in Section 3 below, for as long as you Externally Deploy the Covered Code or twelve (12) months from the date of initial External Deployment, whichever is longer. You should preferably distribute the Source Code of Your Externally Deployed Modifications electronically (e.g. download from a Web site).

2.3 Distribution of Executable Versions. In addition, if You Externally Deploy Covered Code (Original Code and/or Modifications) in object code, executable form only, You must include a prominent notice, in the code itself as well as in related documentation, stating that Source Code of the Covered Code is available under the terms of this License with information on how and where to obtain such Source Code.

2.4 Third Party Rights. You expressly acknowledge and agree that although Apple and each Contributor grants the licenses to their respective portions of the Covered Code set forth herein, no assurances are provided by Apple or any Contributor that the Covered Code does not infringe the patent or other intellectual property rights of any other entity. Apple and each Contributor disclaim any liability to You for claims brought by any other entity based on infringement of intellectual property rights or otherwise. As a condition to exercising the rights and licenses granted hereunder, You hereby assume sole responsibility to secure any other intellectual property rights needed, if any. For example, if a third party patent license is required to allow You to distribute the Covered Code, it is Your responsibility to acquire that license before distributing the Covered Code.

3. Your Grants. In consideration of, and as a condition to, the licenses granted to You under this License, You hereby grant to any person or entity receiving or distributing Covered Code under this License a non-exclusive, royalty-free, perpetual, irrevocable license, under Your Applicable Patent Rights and other intellectual property rights (other than patent) owned or controlled by You, to use, reproduce, display, perform, modify, sublicense, distribute and Externally Deploy Your Modifications of the same scope and extent as Apple's licenses under Sections 2.1 and 2.2 above.

4. Larger Works. You may create a Larger Work by combining Covered Code with other code not governed by the terms of this License and distribute the Larger Work as a single product. In each such instance, You must make sure the requirements of this License are fulfilled for the Covered Code or any portion thereof.

5. Limitations on Patent License. Except as expressly stated in Section 2, no other patent rights, express or implied, are granted by Apple herein. Modifications and/or Larger Works may require additional patent licenses from Apple which Apple may grant in its sole discretion.

6. Additional Terms. You may choose to offer, and to charge a fee for, warranty, support, indemnity or liability obligations and/or other rights consistent with the scope of the license granted herein ("Additional Terms") to one or more recipients of Covered Code.

However, You may do so only on Your own behalf and as Your sole responsibility, and not on behalf of Apple or any Contributor. You must obtain the recipient's agreement that any such Additional Terms are offered by You alone, and You hereby agree to indemnify, defend and hold Apple and every Contributor harmless for any liability incurred by or claims asserted against Apple or such Contributor by reason of any such Additional Terms.

7. Versions of the License. Apple may publish revised and/or new versions of this License from time to time. Each version will be given a distinguishing version number. Once Original Code has been published under a particular version of this License, You may continue to use it under the terms of that version. You may also choose to use such Original Code under the terms of any subsequent version of this License published by Apple. No one other than Apple has the right to modify the terms applicable to Covered Code created under this License.

8. NO WARRANTY OR SUPPORT. The Covered Code may contain in whole or in part pre-release, untested, or not fully tested works. The Covered Code may contain errors that could cause failures or loss of data, and may be incomplete or contain inaccuracies. You expressly acknowledge and agree that use of the Covered Code, or any portion thereof, is at Your sole and entire risk. THE COVERED CODE IS PROVIDED "AS IS" AND WITHOUT WARRANTY, UPGRADES OR SUPPORT OF ANY KIND AND APPLE AND APPLE'S LICENSOR(S) (COLLECTIVELY REFERRED TO AS "APPLE" FOR THE PURPOSES OF SECTIONS 8 AND 9) AND ALL CONTRIBUTORS EXPRESSLY DISCLAIM ALL WARRANTIES AND/OR CONDITIONS, EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES AND/OR CONDITIONS OF MERCHANTABILITY, OF SATISFACTORY QUALITY, OF FITNESS FOR A PARTICULAR PURPOSE, OF ACCURACY, OF QUIET ENJOYMENT, AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. APPLE AND EACH CONTRIBUTOR DOES NOT WARRANT AGAINST INTERFERENCE WITH YOUR ENJOYMENT OF THE COVERED CODE, THAT THE FUNCTIONS CONTAINED IN THE COVERED CODE WILL MEET YOUR REQUIREMENTS, THAT THE OPERATION OF THE COVERED CODE WILL BE UNINTERRUPTED OR ERROR-FREE, OR THAT DEFECTS IN THE COVERED CODE WILL BE CORRECTED. NO ORAL OR WRITTEN INFORMATION OR ADVICE GIVEN BY APPLE, AN APPLE AUTHORIZED REPRESENTATIVE OR ANY CONTRIBUTOR SHALL CREATE A WARRANTY.

You acknowledge that the Covered Code is not intended for use in the operation of nuclear facilities, aircraft navigation, communication systems, or air traffic control machines in which case the failure of the Covered Code could lead to death, personal injury, or severe physical or environmental damage.

9. LIMITATION OF LIABILITY. TO THE EXTENT NOT PROHIBITED BY LAW, IN NO EVENT SHALL APPLE OR ANY CONTRIBUTOR BE LIABLE FOR ANY INCIDENTAL, SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES ARISING OUT OF OR RELATING TO THIS LICENSE OR YOUR USE OR INABILITY TO USE THE COVERED CODE, OR ANY PORTION THEREOF, WHETHER UNDER A THEORY OF CONTRACT, WARRANTY, TORT (INCLUDING NEGLIGENCE), PRODUCTS LIABILITY OR OTHERWISE, EVEN IF APPLE OR SUCH

CONTRIBUTOR HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES AND NOTWITHSTANDING THE FAILURE OF ESSENTIAL PURPOSE OF ANY REMEDY. SOME JURISDICTIONS DO NOT ALLOW THE LIMITATION OF LIABILITY OF INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THIS LIMITATION MAY NOT APPLY TO YOU. In no event shall Apple's total liability to You for all damages (other than as may be required by applicable law) under this License exceed the amount of fifty dollars (\$50.00).

10. Trademarks. This License does not grant any rights to use the trademarks or trade names "Apple", "Apple Computer", "Mac", "Mac OS", "QuickTime", "QuickTime streaming server" or any other trademarks, service marks, logos or trade names belonging to Apple (collectively "Apple Marks") or to any trademark, service mark, logo or trade name belonging to any Contributor. You agree not to use any Apple Marks in or as part of the name of products derived from the Original Code or to endorse or promote products derived from the Original Code other than as expressly permitted by and in strict compliance at all times with Apple's third party trademark usage guidelines which are posted at <http://www.apple.com/legal/guidelinesfor3rdparties.html>.

11. Ownership. Subject to the licenses granted under this License, each Contributor retains all rights, title and interest in and to any Modifications made by such Contributor. Apple retains all rights, title and interest in and to the Original Code and any Modifications made by or on behalf of Apple ("Apple Modifications"), and such Apple Modifications will not be automatically subject to this License. Apple may, at its sole discretion, choose to license such Apple Modifications under this License, or on different terms from those contained in this License or may choose not to license them at all.

12. Termination.

12.1 Termination. This License and the rights granted hereunder will terminate: (a) automatically without notice from Apple if You fail to comply with any term(s) of this License and fail to cure such breach within 30 days of becoming aware of such breach; (b) immediately in the event of the circumstances described in Section 13.5(b); or (c) automatically without notice from Apple if You, at any time during the term of this License, commence an action for patent infringement against Apple; provided that Apple did not first commence an action for patent infringement against You in that instance.

12.2 Effect of Termination. Upon termination, You agree to immediately stop any further use, reproduction, modification, sublicensing and distribution of the Covered Code. All sublicenses to the Covered Code which have been properly granted prior to termination shall survive any termination of this License. Provisions which, by their nature, should remain in effect beyond the termination of this License shall survive, including but not limited to Sections 3, 5, 8, 9, 10, 11, 12.2 and 13. No party will be liable to any other for compensation, indemnity or damages of any sort solely as a result of terminating this License in accordance with its terms, and termination of this License will be without prejudice to any other right or remedy of any party.

13. Miscellaneous.

13.1 Government End Users. The Covered Code is a "commercial item" as defined in FAR 2.101. Government software and technical data rights in the Covered Code include only

those rights customarily provided to the public as defined in this License. This customary commercial license in technical data and software is provided in accordance with FAR 12.211 (Technical Data) and 12.212 (Computer Software) and, for Department of Defense purchases, DFAR 252.227-7015 (Technical Data -- Commercial Items) and 227.7202-3 (Rights in Commercial Computer Software or Computer Software Documentation). Accordingly, all U.S. Government End Users acquire Covered Code with only those rights set forth herein.

13.2 Relationship of Parties. This License will not be construed as creating an agency, partnership, joint venture or any other form of legal association between or among You, Apple or any Contributor, and You will not represent to the contrary, whether expressly, by implication, appearance or otherwise.

13.3 Independent Development. Nothing in this License will impair Apple's right to acquire, license, develop, have others develop for it, market and/or distribute technology or products that perform the same or similar functions as, or otherwise compete with, Modifications, Larger Works, technology or products that You may develop, produce, market or distribute.

13.4 Waiver; Construction. Failure by Apple or any Contributor to enforce any provision of this License will not be deemed a waiver of future enforcement of that or any other provision. Any law or regulation which provides that the language of a contract shall be construed against the drafter will not apply to this License.

13.5 Severability. (a) If for any reason a court of competent jurisdiction finds any provision of this License, or portion thereof, to be unenforceable, that provision of the License will be enforced to the maximum extent permissible so as to effect the economic benefits and intent of the parties, and the remainder of this License will continue in full force and effect. (b) Notwithstanding the foregoing, if applicable law prohibits or restricts You from fully and/or specifically complying with Sections 2 and/or 3 or prevents the enforceability of either of those Sections, this License will immediately terminate and You must immediately discontinue any use of the Covered Code and destroy all copies of it that are in your possession or control.

13.6 Dispute Resolution. Any litigation or other dispute resolution between You and Apple relating to this License shall take place in the Northern District of California, and You and Apple hereby consent to the personal jurisdiction of, and venue in, the state and federal courts within that District with respect to this License. The application of the United Nations Convention on Contracts for the International Sale of Goods is expressly excluded.

13.7 Entire Agreement; Governing Law. This License constitutes the entire agreement between the parties with respect to the subject matter hereof. This License shall be governed by the laws of the United States and the State of California, except that body of California law concerning conflicts of law.

Where You are located in the province of Quebec, Canada, the following clause applies: The parties hereby confirm that they have requested that this License and all related documents be drafted in English. Les parties ont exigé que le présent contrat et tous les documents connexes soient rédigés en anglais.

EXHIBIT A.

"Portions Copyright (c) 1999-2003 Apple Computer, Inc. All Rights Reserved.

This file contains Original Code and/or Modifications of Original Code as defined in and that are subject to the Apple Public Source License Version 2.0 (the 'License'). You may not use this file except in compliance with the License. Please obtain a copy of the License at <http://www.opensource.apple.com/apsl/> and read it before using this. The Original Code and all software distributed under the License are distributed on an 'AS IS' basis, WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, AND APPLE HEREBY DISCLAIMS ALL SUCH WARRANTIES, INCLUDING WITHOUT LIMITATION, ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, QUIET ENJOYMENT OR NON-INFRINGEMENT.

Please see the License for the specific language governing rights and limitations under the License."

FFmpeg Project

GNU LESSER GENERAL PUBLIC LICENSE Version 2.1, February 1999 Copyright (C) 1991, 1999 Free Software Foundation, Inc.

51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

[This is the first released version of the Lesser GPL. It also counts as the successor of the GNU Library Public License, version 2, hence the version number 2.1.]

Preamble The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public Licenses are intended to guarantee your freedom to share and change free software--to make sure the software is free for all its users.

This license, the Lesser General Public License, applies to some specially designated software packages--typically libraries--of the Free Software Foundation and other authors who decide to use it. You can use it too, but we suggest you first think carefully about whether this license or the ordinary General Public License is the better strategy to use in any particular case, based on the explanations below.

When we speak of free software, we are referring to freedom of use, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you want); that you receive source code or can get it if you want it; that you can change the software and use pieces of it in new free programs; and that you are informed that you can do these things.

To protect your rights, we need to make restrictions that forbid distributors to deny you these rights or to ask you to surrender these rights. These restrictions translate to certain responsibilities for you if you distribute copies of the library or if you modify it.

For example, if you distribute copies of the library, whether gratis or for a fee, you must give the recipients all the rights that we gave you. You must make sure that they, too, receive or can get the source code. If you link other code with the library, you must

provide complete object files to the recipients, so that they can relink them with the library after making changes to the library and recompiling it. And you must show them these terms so they know their rights.

We protect your rights with a two-step method: (1) we copyright the library, and (2) we offer you this license, which gives you legal permission to copy, distribute and/or modify the library.

To protect each distributor, we want to make it very clear that there is no warranty for the free library. Also, if the library is modified by someone else and passed on, the recipients should know that what they have is not the original version, so that the original author's reputation will not be affected by problems that might be introduced by others.

Finally, software patents pose a constant threat to the existence of any free program. We want to make sure that a company cannot effectively restrict the users of a free program by obtaining a restrictive license from a patent holder. Therefore, we insist that any patent license obtained for a version of the library must be consistent with the full freedom of use specified in this license.

Most GNU software, including some libraries, is covered by the ordinary GNU General Public License. This license, the GNU Lesser General Public License, applies to certain designated libraries, and is quite different from the ordinary General Public License. We use this license for certain libraries in order to permit linking those libraries into non-free programs.

When a program is linked with a library, whether statically or using a shared library, the combination of the two is legally speaking a combined work, a derivative of the original library. The ordinary General Public License therefore permits such linking only if the entire combination fits its criteria of freedom. The Lesser General Public License permits more lax criteria for linking other code with the library.

We call this license the "Lesser" General Public License because it does Less to protect the user's freedom than the ordinary General Public License. It also provides other free software developers Less of an advantage over competing non-free programs. These disadvantages are the reason we use the ordinary General Public License for many libraries. However, the Lesser license provides advantages in certain special circumstances.

For example, on rare occasions, there may be a special need to encourage the widest possible use of a certain library, so that it becomes a de-facto standard. To achieve this, non-free programs must be allowed to use the library. A more frequent case is that a free library does the same job as widely used non-free libraries. In this case, there is little to gain by limiting the free library to free software only, so we use the Lesser General Public License.

In other cases, permission to use a particular library in non-free programs enables a greater number of people to use a large body of free software. For example, permission to use the GNU C Library in non-free programs enables many more people to use the whole GNU operating system, as well as its variant, the GNU/Linux operating system.

Although the Lesser General Public License is Less protective of the users' freedom, it does ensure that the user of a program that is linked with the Library has the freedom and the wherewithal to run that program using a modified version of the Library.

The precise terms and conditions for copying, distribution and modification follow. Pay close attention to the difference between a "work based on the library" and a "work that uses the library". The former contains code derived from the library, whereas the latter must be combined with the library in order to run.

GNU LESSER GENERAL PUBLIC LICENSE TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION This License Agreement applies to any software library or other program which contains a notice placed by the copyright holder or other authorized party saying it may be distributed under the terms of this Lesser General Public License (also called "this License").

Each licensee is addressed as "you".

A "library" means a collection of software functions and/or data prepared so as to be conveniently linked with application programs (which use some of those functions and data) to form executables.

The "Library", below, refers to any such software library or work which has been distributed under these terms. A "work based on the Library" means either the Library or any derivative work under copyright law: that is to say, a work containing the Library or a portion of it, either verbatim or with modifications and/or translated straightforwardly into another language. (Hereinafter, translation is included without limitation in the term "modification".) "Source code" for a work means the preferred form of the work for making modifications to it. For a library, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the library.

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running a program using the Library is not restricted, and output from such a program is covered only if its contents constitute a work based on the Library (independent of the use of the Library in a tool for writing it). Whether that is true depends on what the Library does and what the program that uses the Library does.

1. You may copy and distribute verbatim copies of the Library's complete source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and distribute a copy of this License along with the Library.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

2. You may modify your copy or copies of the Library or any portion of it, thus forming a work based on the Library, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions: a) The modified work must itself be a software library.

b) You must cause the files modified to carry prominent notices stating that you changed the files and the date of any change.

c) You must cause the whole of the work to be licensed at no charge to all third parties under the terms of this License.

d) If a facility in the modified Library refers to a function or a table of data to be supplied by an application program that uses the facility, other than as an argument passed when the facility is invoked, then you must make a good faith effort to ensure that, in the event an application does not supply such function or table, the facility still operates, and performs whatever part of its purpose remains meaningful.

(For example, a function in a library to compute square roots has a purpose that is entirely well-defined independent of the application. Therefore, Subsection 2d requires that any application-supplied function or table used by this function must be optional: if the application does not supply it, the square root function must still compute square roots.) These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Library, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Library, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Library.

In addition, mere aggregation of another work not based on the Library with the Library (or with a work based on the Library) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may opt to apply the terms of the ordinary GNU General Public License instead of this License to a given copy of the Library. To do this, you must alter all the notices that refer to this License, so that they refer to the ordinary GNU General Public License, version 2, instead of to this License. (If a newer version than version 2 of the ordinary GNU General Public License has appeared, then you can specify that version instead if you want.) Do not make any other change in these notices.

Once this change is made in a given copy, it is irreversible for that copy, so the ordinary GNU General Public License applies to all subsequent copies and derivative works made from that copy.

This option is useful when you want to copy part of the code of the Library into a program that is not a library.

4. You may copy and distribute the Library (or a portion or derivative of it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange.

If distribution of object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place satisfies the requirement to distribute the source code, even though third parties are not compelled to copy the source along with the object code.

5. A program that contains no derivative of any portion of the Library, but is designed to work with the Library by being compiled or linked with it, is called a "work that uses the Library". Such a work, in isolation, is not a derivative work of the Library, and therefore falls outside the scope of this License.

However, linking a "work that uses the Library" with the Library creates an executable that is a derivative of the Library (because it contains portions of the Library), rather than a "work that uses the library". The executable is therefore covered by this License.

Section 6 states terms for distribution of such executables.

When a "work that uses the Library" uses material from a header file that is part of the Library, the object code for the work may be a derivative work of the Library even though the source code is not.

Whether this is true is especially significant if the work can be linked without the Library, or if the work is itself a library. The threshold for this to be true is not precisely defined by law.

If such an object file uses only numerical parameters, data structure layouts and accessors, and small macros and small inline functions (ten lines or less in length), then the use of the object file is unrestricted, regardless of whether it is legally a derivative work. (Executables containing this object code plus portions of the Library will still fall under Section 6.) Otherwise, if the work is a derivative of the Library, you may distribute the object code for the work under the terms of Section 6.

Any executables containing that work also fall under Section 6, whether or not they are linked directly with the Library itself.

6. As an exception to the Sections above, you may also combine or link a "work that uses the Library" with the Library to produce a work containing portions of the Library, and distribute that work under terms of your choice, provided that the terms permit modification of the work for the customer's own use and reverse engineering for debugging such modifications.

You must give prominent notice with each copy of the work that the Library is used in it and that the Library and its use are covered by this License. You must supply a copy of this License. If the work during execution displays copyright notices, you must include the copyright notice for the Library among them, as well as a reference directing the user to the copy of this License. Also, you must do one of these things: a) Accompany the work with the complete corresponding machine-readable source code for the Library including whatever changes were used in the work (which must be distributed under Sections 1 and 2 above); and, if the work is an executable linked with the Library, with the complete machine-readable "work that uses the Library", as object code and/or source code, so that the user can modify the Library and then relink to produce a modified executable containing the modified Library. (It is understood that the user who changes the contents of definitions files in the Library will not necessarily be able

to recompile the application to use the modified definitions.) b) Use a suitable shared library mechanism for linking with the Library. A suitable mechanism is one that (1) uses at run time a copy of the library already present on the user's computer system, rather than copying library functions into the executable, and (2) will operate properly with a modified version of the library, if the user installs one, as long as the modified version is interface-compatible with the version that the work was made with.

c) Accompany the work with a written offer, valid for at least three years, to give the same user the materials specified in Subsection 6a, above, for a charge no more than the cost of performing this distribution.

d) If distribution of the work is made by offering access to copy from a designated place, offer equivalent access to copy the above specified materials from the same place.

e) Verify that the user has already received a copy of these materials or that you have already sent this user a copy.

For an executable, the required form of the "work that uses the Library" must include any data and utility programs needed for reproducing the executable from it. However, as a special exception, the materials to be distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

It may happen that this requirement contradicts the license restrictions of other proprietary libraries that do not normally accompany the operating system. Such a contradiction means you cannot use both them and the Library together in an executable that you distribute.

7. You may place library facilities that are a work based on the Library side-by-side in a single library together with other library facilities not covered by this License, and distribute such a combined library, provided that the separate distribution of the work based on the Library and of the other library facilities is otherwise permitted, and provided that you do these two things: a) Accompany the combined library with a copy of the same work based on the Library, uncombined with any other library facilities. This must be distributed under the terms of the Sections above.

b) Give prominent notice with the combined library of the fact that part of it is a work based on the Library, and explaining where to find the accompanying uncombined form of the same work.

8. You may not copy, modify, sublicense, link with, or distribute the Library except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, link with, or distribute the Library is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

9. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Library or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore,

by modifying or distributing the Library (or any work based on the Library), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Library or works based on it.

10. Each time you redistribute the Library (or any work based on the Library), the recipient automatically receives a license from the original licensor to copy, distribute, link with or modify the Library subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein.

You are not responsible for enforcing compliance by third parties with this License.

11. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Library at all. For example, if a patent license would not permit royalty-free redistribution of the Library by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Library.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply, and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

12. If the distribution and/or use of the Library is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Library under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.

13. The Free Software Foundation may publish revised and/or new versions of the Lesser General Public License from time to time.

Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Library specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Library does not specify a license version number, you may choose any version ever published by the Free Software Foundation.

14. If you want to incorporate parts of the Library into other free programs whose distribution conditions are incompatible with these, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY 15. BECAUSE THE LIBRARY IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE LIBRARY, TO THE EXTENT PERMITTED BY APPLICABLE LAW.

EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE LIBRARY "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE LIBRARY IS WITH YOU. SHOULD THE LIBRARY PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

16. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE LIBRARY AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE LIBRARY (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE LIBRARY TO OPERATE WITH ANY OTHER SOFTWARE), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Index

A

Activation **30**
Adding New Source **84**
Adding Titles **83**
Aspect Ratio **113**
Asset Manager, using to re-assign media **181**
AutoLive **74**

B

Bandwidth **222**
Basics Concepts **34**
Begin Playing Control **120**
Broadcast Configuration **195**
Broadcasting **57**

C

Canadian EMC Notice of Compliance **12**
Canvas Size **192**
Capture Cards **140**
Changing Font **87**
Changing Font Color **87**
Changing Justification **87**
Configuring Titles **85**
copyright notice **11**
Countdown Clock **65**
Creating New Templates **88**

D

Deactivate Serial Numbers **177**
Demonstration Mode **177**
Desktop Presenter **68**

E

Edit Menu **184**
Editing Shots **46**
Editing XML Files **88**
Encoder Presets **196**
Encoder Presets Window **211**
Encoder Settings **222**

F

File Menu **184**
File Sources **68**
Filter Parameters **122**
Flash H.264 **216**
Flash To Livestream **204**
Flash To Ustream **201, 204**

G

Global Logos **89**
Good Lighting **220**

H

H.264 **213**
Hardware Audio **171**
HDV Serial **177**
Help Menu **189**
High Quality Audio **220**
High Quality Video **116**

I

Inspector **102**
Inspector vs. Editor **102**
Installation **29**

L

Layers **71**
 Layout Menu **187**
 license requirements, for MPEG-2 **11**
 Licenses **176**
 Live Feed Sources **109**
 Live Icon **68**
 Live Icon Settings **175**
 Live Playback **119**
 Live Sources **67**
 Look Tab **127**

M

Manual Activation **177**
 Matte **112**
 Media File Sources **110**
 Media Menu **185**
 media, re-assigning with Asset Manager **181**
 Modifying Titles **86**
 Motion **222**
 MPEG-2, license requirements **11**
 Multicast **199**
 Multiple Broadcast Settings **195**

N

notices, legal, generally **11**

O

Opacity **112**

P

Pipelines **125**
 Placing Titles **87**
 Playlist **145**
 Preferences, Accessing **173**
 Preferences, Advanced **178**
 Preferences, Resetting **174**
 Presenter Is Operator **19**
 Preview / Live Area **63**

R

re-assigning media with Asset Manager **181**
 Remember Position Control **121**

Reposition Buttons **113**

S

Scoreboards **125**
 Scripting **27**
 Scrubbing **119**
 Serial Numbers **176**
 Shot Audio **68, 170, 171**
 Shot Audio, Adding Sources **171**
 Shot Audio, Managing Sources **172**
 Shot Editor Chroma Key **114**
 Shot Editor Cropping **114**
 Shot Editor Effects **111**
 Shot Editor Filter **121**
 Shot Editor Layout **103**
 Shot Editor Media Panel **109**
 Shot Editor Motion **117**
 Shot Editor Playback **118**
 Shot Editor Preview **107**
 Shot Graphics **68**
 Shot Logos **96**
 Shot Selection Area **68**
 Shot, Moving **71**
 Shots, Changing **69**
 Software Update **178**
 Source Visibility **107**
 Sources **104**
 Sources Menu **186**
 Switch Menu **185**

T

Telestream
 contacting **13**
 Templates **104**
 Title Area **86**
 Title Banner Sources **110**
 Tool Bar **67**
 trademark notice **11**
 Transition Controls **65**
 Transition Editing **66**
 Transition Time **66**
 Transport Controls **119**
 Triangular Lighting **221**
 Turning Layers On and Off **96**

U

Unicast **199**

Uninstalling **31**

USB Devices **143**

V

Virtual Camera **193**

Virtual Sets **106**

W

warranty **12**

Warranty and Disclaimers **12**

When Finished Control **120**

Window Menu **188**

Windows Media **81**

Y

YUV Colorspace **179**

